

# Packet Tracer - Configure Router-on-a-Stick Inter-VLAN Routing

Name: Danica Marie A. Dumalagan

**Date:** March 2, 2023

# **Addressing Table**

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
R1	G0/0.10	172.17.10.1	255.255.255.0	N/A
	G0/0.30	172.17.30.1	255.255.255.0	
PC1	NIC	172.17.10.10	255.255.255.0	172.17.10.1
PC2	NIC	172.17.30.10	255.255.255.0	172.17.30.1

# **Objectives**

Part 1: Add VLANs to a Switch

Part 2: Configure Subinterfaces

Part 3: Test Connectivity with Inter-VLAN Routing

### **Scenario**

In this activity, you will configure VLANs and inter-VLAN routing. You will then enable trunk interfaces and verify connectivity between VLANs.

#### Instructions

### Part 1: Add VLANs to a Switch

#### Step 1: Create VLANs on S1.

Create VLAN 10 and VLAN 30 on S1.

## Step 2: Assign VLANs to ports.

- a. Configure interfaces F0/6 and F0/11 as access ports and assign VLANs.
  - Assign the port connected to **PC1** to VLAN 10.
  - Assign the port connected to PC3 to VLAN 30.
- b. Issue the **show vlan brief** command to verify VLAN configuration.

## S1# show vlan brief

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4
			Fa0/5, Fa0/7, Fa0/8, Fa0/9
			Fa0/10, Fa0/12, Fa0/13, Fa0/14

```
Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                Fa0/23, Fa0/24, Gig0/1, Gig0/2
10
   VLAN0010
                                               Fa0/11
                                      active
30 VLAN0030
                                      active
                                               Fa0/6
1002 fddi-default
                                      active
1003 token-ring-default
                                      active
1004 fddinet-default
                                      active
1005 trnet-default
                                      active
```

## Step 3: Test connectivity between PC1 and PC3.

From PC1, ping PC3.

Were the pings successful? Why did you get this result?

No, because PC1 and PC3 belong to different VLANs

## Part 2: Configure Subinterfaces

## Step 1: Configure subinterfaces on R1 using the 802.1Q encapsulation.

- a. Create the subinterface G0/0.10.
  - Set the encapsulation type to 802.1Q and assign VLAN 10 to the subinterface.
  - Refer to the Address Table and assign the correct IP address to the subinterface.

```
R1(config) # int g0/0.10
R1(config-subif) # encapsulation dot1Q 10
R1(config-subif) # ip address 172.17.10.1 255.255.255.0
```

b. Repeat for the G0/0.30 subinterface.

# Step 2: Verify Configuration.

- a. Use the **show ip interface brief** command to verify subinterface configuration. Both subinterfaces are down. Subinterfaces are virtual interfaces that are associated with a physical interface. Therefore, in order to enable subinterfaces, you must enable the physical interface that they are associated with.
- b. Enable the G0/0 interface. Verify that the subinterfaces are now active.

# Part 3: Test Connectivity with Inter-VLAN Routing

### Step 1: Ping between PC1 and PC3.

From PC1, ping PC3. The pings should still fail. Explain.

A trunk port has not yet been configured.

# Step 2: Enable trunking.

a. On S1, issue the show vlan command.

What VLAN is G0/1 assigned to?

VLAN 1 default

b. Because the router was configured with multiple subinterfaces assigned to different VLANs, the switch port connecting to the router must be configured as a trunk. Enable trunking on interface G0/1.

How can you determine that the interface is a trunk port using the **show vlan** command?

G0/1 is not listed in the show vlan list

Issue the show interface trunk command to verify that the interface is configured as a trunk.

### **Step 3: Test Connectivity**

If the configurations are correct, PC1 and PC3 should be able to ping their default gateways and each other.

What addresses do PC1 and PC3 use as their default gateway addresses?

Both are using the IP addresses of the subinterface

## Part 4: Post your screenshots

On the PT Activity window, make sure that the completion grade is **100%**. Click on the **Check Results** button and select the **Assessment Items** tab. Take a screen shot of the whole window, showing the table of assessment items, and the score/item count. Own your photo by placing a watermark on your photo with your name and USC ID Number. Paste your screenshot below:

