DDL – Data Definition Language



DDL – Data Definition Language

ALTER <OBJECT_TYPE> <OBJECT_NAME>

ADD / DROP ... <OBJECT_TYPE> **...**

ALTER AGGREGATE — change the definition of an aggregate function
ALTER COLLATION — change the definition of a collation
ALTER CONVERSION — change the definition of a conversion
ALTER DATABASE — change a database
ALTER DEFAULT PRIVILEGES — define default access privileges
ALTER DOMAIN — change the definition of a domain
ALTER EVENT TRIGGER — change the definition of an event trigger
ALTER EXTENSION — change the definition of an extension
ALTER FOREIGN DATA WRAPPER — change the definition of a foreign-data wrapper
ALTER FOREIGN TABLE — change the definition of a foreign table
ALTER FUNCTION — change the definition of a function
ALTER GROUP — change role name or membership
ALTER INDEX — change the definition of an index
ALTER LANGUAGE — change the definition of a procedural language
ALTER LARGE OBJECT — change the definition of a large object
ALTER MATERIALIZED VIEW — change the definition of a materialized view
ALTER OPERATOR — change the definition of an operator
ALTER OPERATOR CLASS — change the definition of an operator class
ALTER OPERATOR FAMILY — change the definition of an operator family
ALTER POLICY — change the definition of a row level security policy
ALTER PROCEDURE — change the definition of a procedure
ALTER PUBLICATION — change the definition of a publication
ALTER ROLE — change a database role
ALTER ROUTINE — change the definition of a routine
ALTER RULE — change the definition of a rule
ALTER SCHEMA — change the definition of a schema
ALTER SEQUENCE — change the definition of a sequence generator
ALTER SERVER — change the definition of a foreign server
ALTER STATISTICS — change the definition of an extended statistics object
ALTER SUBSCRIPTION — change the definition of a subscription
ALTER SYSTEM — change a server configuration parameter
ALTER TABLE — change the definition of a table
ALTER TABLESPACE — change the definition of a tablespace
ALTER TEXT SEARCH CONFIGURATION — change the definition of a text search configuration
ALTER TEXT SEARCH DICTIONARY — change the definition of a text search dictionary
ALTER TEXT SEARCH PARSER — change the definition of a text search parser
ALTER TEXT SEARCH TEMPLATE — change the definition of a text search template
ALTER TRIGGER — change the definition of a trigger
ALTER TYPE — change the definition of a type
ALTER USER — change a database role
ALTER USER MAPPING — change the definition of a user mapping
ALTER VIEW — change the definition of a view

https://www.postgresql.org/docs/12/sql-commands.html

DDL – ALTER TABLE

```
ALTER TABLE [ IF EXISTS ] [ ONLY ] name [ * ]
    action [, ... ]
ALTER TABLE [ IF EXISTS ] [ ONLY ] name [ * ]
    RENAME [ COLUMN ] column_name TO new_column_name
ALTER TABLE [ IF EXISTS ] [ ONLY ] name [ * ]
    RENAME CONSTRAINT constraint_name TO new_constraint_name
ALTER TABLE [ IF EXISTS ] name
    RENAME TO new_name
ALTER TABLE [ IF EXISTS ] name
    SET SCHEMA new_schema
ALTER TABLE ALL IN TABLESPACE name [ OWNED BY role_name [, ... ] ]
    SET TABLESPACE new_tablespace [ NOWAIT ]
ALTER TABLE [ IF EXISTS ] name
    ATTACH PARTITION partition_name { FOR VALUES partition_bound_spec | DEFAULT }
ALTER TABLE [ IF EXISTS ] name
    DETACH PARTITION partition_name
```

https://www.postgresql.org/docs/12/sql-altertable.html