

🌙 WD003 Week 6 — English Worksheet

Topic: JavaScript Dark Mode Toggle · **Course:** Portfolio Site · **Time:** about 45 minutes

This week you add a **dark mode** button with JavaScript. The trick is simple: clicking the button **toggles one class** (`.dark`) on the `<body>` , and your CSS does the rest. As a bonus, you save the choice in `localStorage` so the site remembers it next time.

`classList.toggle("dark")` flips the class on and off — on if it is missing, off if it is there.
`classList.contains("dark")` checks whether it is currently on.

1 · Predict 🧠

Read each block of code. Before you imagine the page, write what you think will happen.

```
btn.addEventListener("click", function() {
  document.body.classList.toggle("dark");
});
```

The body starts with no `.dark` class. The visitor clicks the button once, then a second time. What is on the body after each click?


```
body { background-color: white; color: black; }
body.dark { background-color: #1a1a1a; color: #f0f0f0; }
```

When `.dark` is added to the body, which colors win — the first rule or the second? What does the page look like?


```
if (document.body.classList.contains("dark")) {  
  btn.textContent = "Light Mode";  
} else {  
  btn.textContent = "Dark Mode";  
}
```

The site is currently in dark mode. What does the button say? What should it say so the label makes sense?

2 · Spot the Bug 🐛

Each block of code below was meant to do something, but it is broken. Read what the code is **supposed** to do, then rewrite it so it works. After that, explain why the original was wrong and why your fix works.

Bug A — Clicking the button is supposed to flip dark mode on and off. Right now clicking it does nothing at all.

```
let btn = document.querySelector("#darkBtn");
btn.classList.toggle("dark");
```

Hint: the toggle should happen *when the button is clicked*, and it should change the **body**, not the button.

Write the fixed code:

Why was it wrong? Why does your fix work?

Bug B — Dark mode is supposed to *switch back and forth* each click. Right now it only ever turns dark on, and never off.

```
btn.addEventListener("click", function() {
  document.body.classList.add("dark");
});
```

Hint: `add` only ever adds. There is a method that flips instead.

Write the fixed code:

Why was it wrong? Why does your fix work?

Bug C — When dark mode is on, the button is supposed to say "Light Mode" so the visitor knows what clicking it will do. Right now the labels are swapped.

```
if (document.body.classList.contains("dark")) {  
  btn.textContent = "Dark Mode";  
} else {  
  btn.textContent = "Light Mode";  
}
```

Hint: the label should describe what the button *switches to*, not what it is now.

Write the fixed code:

Why was it wrong? Why does your fix work?

Open your site and add a working dark mode toggle.

1. Add a **button** with an id (for example `id="darkBtn"`).
2. In CSS, write a `body.dark` rule with a dark background and light text. Don't forget your project cards.
3. In JavaScript, **toggle** the `.dark` class on the body when the button is clicked.
4. Update the button's text so it says "Dark Mode" or "Light Mode" depending on the current state.
5. **Bonus:** save the choice in `localStorage` so a refresh keeps the same mode.

When you finish, send **photos or a video** of both light and dark mode, then explain what you did.

Use these sentence starters — write 4 to 6 sentences total.

My dark mode button toggles ...

When `.dark` is on the body, the page ...

I made the button text change by ...

The hardest part was ...

To fix it, I ...

(If you tried the bonus) localStorage helped me by ...

4 · Record Your Walkthrough 🎥

Now take a video on your phone (or a parent's phone) while you toggle dark mode. Talk through it like you are teaching someone who has never written JavaScript. Try to use these words: **toggle**, **class**, **click**, **dark mode**, **button**.

1. Show your site in light mode, then click the button to go dark.
2. Read your `toggle` line out loud and say what it changes.
3. Show the button's text changing between the two modes.
4. Show one bug you hit and how you fixed it.

Write what you will say in your video. Use the space below to plan it before you record — you can read from it while filming.

Submit ✓

Send this worksheet + your walkthrough video to teacher on KakaoTalk.