- Prosesu copy Sistema Operativu ba flas liu husi DOS/CMD
- Primeiru ita loke uluk CMD: prosesu atu loke CMD iha rua maibe w uza ida deit ne'ebe fasil liu mak hanesan, ita hanehan iha butaun Star no Butaun R dala ida deit no nia janela mak hanesan iha kraik ne'e:




Depois nia mosu tan janela ida no ita hakerek CMD, hotu ita hili OK no nia janela mak hanesan iha kraik ne'e:



Depois mak nia mosu tan janela CMD/Command Prompt, no nia janela mak hanesan iha kraik ne'e :




Hafoin mak ita hakerek DISKPAR depois ita hanehan butaun Enter no nia janela mak hanesan iha kraik ne'e :




Depois de Enter nia mosu tan janela ida hodi haruka ita atu hili obsaun rua Yes atu tama DISKPAR no No la tama DISKPAR no ita hili Yes no nia janela mak hanesan iha kraik ne'e:






Hafoin mak ita hakere LIST DISK no ita Enter nia mosu Lista husi Disk nia no nia janela mak hanesan iha kraik ne'e :




Depois mak ita hakerek, SELECT DISK 1, katak ita hili DISK 1 ne mak ita nia flash, hotu ita hanehan butaun Enter no nia janela mak hanesan iha kraik ne'e :




Depois ita hakerek CLEAN atu hamos Flash, no ita hanehan butaun Enter, no nia janela mak hanesan iha kraik ne'e:




Depois mak ita hakerek, CREATE PARTITION PRIMARY, hotu ita hanehan butaun Enter, no nia janela mak hanesan iha kraik ne'e :



Depois mak ita hakerek, SELECT PARTITION 1, hotu hanehan butaun Enter no nia janela mak hanesan iha kraik ne'e :



Depois ita hakerek tan ACTIVE, hotu Enter no nia janela mak hanesan iha kraik ne'e:



Depois ita hakerek tan, FORMAT FS = NTFS, atu format ita nia flash, no hanehan butaun Enter, no nia komesa format ita nia flash no iha processu kleur uitoan, no ita presisa hein to nia processu to 100, no nia janela mak hanesan iha kraik ne'e:

```
C:\Us
```


Depois ita hein to nia processu hotu, no ita hakerek tan ASSING, hafoin ita hanehan Enter, no nia janela mak hanesan iha kraik ne'e :

Depois ita hakerek tan EXIT, hafoin ita hanehan Enter atu taka DISKPAR no nia janela mak hanesan iha kraik ne'e :

```
C: C:\Windows\system32\cmd.exe - DISKPART


Microsoft Windows [Uersion 6.1.7601]
Commists (c) 2000 Microsoft Commonation 011 mights resemble (c) 2000 Microsoft Commonation 011 mights (c) 2000 Microsoft Commonation 011 mights (c) 2000 Microsoft Commonation 011 mights (c) 2000 Microsoft Commonation (c) 2000 Micros
```

Depois ita hakere tan EXIT, hafoin ita hanehan butaun Enter atu taka CMD, no nia janela mak hanesan iha kraik ne'e :




Depois mak ita copy SO ba iha flash, uza copy babain, hanesan mos ita copy ita nia domentus sira.


Primeir ita loke uluk CD/DVD ne'ebe iha SO, no nia janela mak hanesan iha kraik ne'e:




Depois mak ita Blok tia file sira hotu ita CD/DVD nia laran hafoin mak ita Klik Kanan hodi hili Copy, no nia janela mak hanesan iha kraik ne'e:



Depois ita loke flash no ita paste no nia mosu tan janela ida hodi hatudu prosesu copy nian, no ita hein deit to nia processu remata, no nia janela mak hanesan iha kraik ne'e:





Depois de nia prosesu copy nian hotu ona, no ita nia flash ita bele uza ona ba intalasaun windows. No nia janela mak hanesan iha kraik ne'e :

