
Documentation – instrument-2

Controls

Video input



drop a video file here – Text in the field where any video can be dragged and dropped

Video – Switches the tool's video input to video (must be inserted first)


Camera – Switches the tool's video input to camera (requires selecting a camera via the **Dropdown Menu**)


Off – Turns off the video input

Dropdown Menu – Allows selection of a video source for the **Camera** option

Playbar – Control element for playing, stopping, and looping the inserted video (functional only for **Video** input)

Sequencer





Reset – Returns the step to position 1

Transport On/Off – Turns the Transport (and sequencer) on/off

Tempo Automation – Turns tempo control using video data on/off

BPM – Displays the current tempo and allows tempo control if tempo automation from video data is off

R, G, B switch – Selects the layer for obtaining data from the video

Normal, Inverse, Mean, InvMean switch – Sets the scaling method for video data for the fifth sequencer track

X/Y slider – Selects the portion of the video matrix from which data is obtained

Waveform display – By dropping an audio sample onto this indicator, its waveform is displayed, and the sample is saved to the memory of the specific track

Start – Determines the time in the sample from which playback begins (automation from video data can be toggled on/off using the switch)

Speed – Determines the playback speed of the sample (automation from video data can be toggled on/off using the switch)

Pan – Determines the placement of the sample in the stereo base (automation from video data can be toggled on/off using the switch)

FX – Determines the ratio of the signal sent to the effects unit (automation from video data can be toggled on/off using the switch)

Steps – Sets the current number of steps in the sequencer unit (automation from video data can be toggled on/off using the switch)

1/4, 1/8, 1/16, 1/32, 1/64 switch – Sets the duration of one sequencer step

On/Off switch (pro jednotlivé kroky) – Turns a given step on/off

Gain – Sets the gain of the track

Effects unit



Automation (all effects) – Turns on/off parameter control using video data

On/Off (all effects) – Turns the effect on/off

Dry/Wet (all effects with an exception of Frequency shifter and Filter) – Sets the ratio between processed and unprocessed signal

Hz (Frequency shifter) – Determines how many Hz the spectrum is shifted (range: -1500 Hz to 3000 Hz)

Distortion (Waveshaper) – Sets the value by which the signal is multiplied in a nonlinear function (range: 1 to 30)

Freq (Waveshaper) – Sets the frequency of a band-stop filter (range: 0 Hz to 20 kHz)

Arctan, Sinus switch (Waveshaper) – Determines the function the processed signal passes through

Gain (Chorus) – Adjusts the output volume of the effect (range: -∞ dB to +30 dB)

Freq (Chorus) – Sets the frequency of the low-frequency oscillator (range: 0.1 Hz to 20 Hz)

Feedback (Delay) – Sets the feedback gain (range: 0 to 1)

Time L, Time R (Delay) – Sets the delay for the right and left channels (range: 0 ms to 10 s)

Pre – Delay (Reverb) – Sets the delay before the first reflection arrives (range: 0 ms to 1 s)

Decay (Reverb) – Sets the Decay parameter of the Reverb effect (range: 1 ms to 60 s)


Freq (Filter) – Sets the filter frequency (range: 0 Hz to 20 kHz)

Res (Filter) – Sets the filter resonance (cannot be influenced by video parameters)

Type (Filter) – Sets the filter type (options: low-pass, high-pass, band-pass, and band-stop; cannot be influenced by video data)

Dry/Wet (FX Dry/Wet) – Determines the ratio between the signal that has passed through the effects unit and the signal that has not

Output unit



Out Gain – Potentiometer for adjusting the output signal volume

Pan L a Pan R – Potentiometers for setting the distribution of the left and right channel signals in the stereo base

Create a file – Clicking opens a menu to create and save a recorded audio file

Record – Clicking starts recording (a file must first be created using the **Create a file** control), clicking off stops recording

Driver/Sample Rate – Use the dropdown menu to select an audio driver and sample rate

Initial setup

To play a sound it is needed to **insert (drag and drop) a sample into the designated field (1)** and **ensure at least one step in the sequencer (2) is turned on** for the given sample. **Turn on Transport (3)**. For automating sampler and sequencer parameters using video data **turn on any automation (4)** and **turn on the video input (5)**.

