

To control initial and later transform values in the MUI `Slide` component, use the `in` prop to toggle state, combined with `direction` ('left', 'right', 'up', 'down'), and customize the entrance/exit behavior using the `easing` or `timeout` props. For custom initial positions, wrap the component and apply CSS transitions or custom style overrides.  Magic UI +3

Key Methods to Control Slide Transform Values:

- **Standard Usage:** Use the `in` prop (boolean) to trigger the animation. The component automatically handles the translate transform from off-screen to its final position.

jsx



```
<Slide in={checked} direction="up">
  <div>Content to Slide</div>
</Slide>
```

- **Customizing Transition (Duration/Easing):** Use the `timeout` prop for duration and `easing` prop for CSS timing functions.

jsx



```
<Slide in={checked} timeout={{ enter: 500, exit: 300 }} easing={{ enter: 'ease-out', ex
  <div>Custom Timing</div>
</Slide>
```

- **Initial/Custom Position (CSS):** To change where it starts (e.g., further off-screen), use the `style` prop or `sx` prop to define the initial `transform`.

jsx



```
<Slide in={checked} direction="right">
  <div style={{ transform: 'translateX(-100px)' }}> /* Custom Initial */
    Custom Starting Point
  </div>
</Slide>
```

 GeeksforGeeks +4

Example Implementation:

jsx



```
import React, { useState } from 'react';
import { Slide, Button, Box } from '@mui/material';

export default function SlideExample() {
  const [checked, setChecked] = useState(false);

  return (
    <Box>
      <Button onClick={() => setChecked(!checked)}>Toggle Slide</Button>
      <Slide in={checked} direction="down" timeout={400}>
        <Box sx={{ p: 2, bgcolor: 'primary.main', color: 'white' }}>
          Slide Content
        </Box>
      </Slide>
    </Box>
  );
}
```

- **in** : Controls visibility.
- **direction** : Determines the slide direction ('left', 'right', 'up', 'down').
- **timeout** : Defines the speed of the animation in milliseconds. [GeeksforGeeks +4](#)