```
SHELL = bash
CONFIG_FILE := $(PWD)/.config
-include $(CONFIG_FILE)
EXTRA\_CFLAGS += -I\$(PWD)
export EXTRA_CFLAGS
ifeq ((CONFIG_PXA955), y)
CONFIG_PXA9XX=y
endif
ifeq ($(CONFIG PXA950), y)
CONFIG_PXA9XX=y
endif
ifeq ($(CONFIG_PXA920), y)
CONFIG_PXA9XX=y
endif
ifeq ($(CONFIG_PXA9XX),
EXTRA_CFLAGS += -DPXA9XX
ifeq ($(CONFIG_PXA955), y)
EXTRA_CFLAGS += -DPXA955
KERNELDIR ?= /home/marvell/pxa 955/pxa955 froyo 147/kernel/kernel
CROSS_COMPILE ?=
/home/marvell/pxa_955/pxa955_froyo_147/prebuilt/linux-x86/toolchain/arm-eabi-4.4.0/bin/arm-eabi-
ifeq ($(CONFIG_PXA950), y)
EXTRA CFLAGS += -DPXA950
KERNELDIR ?= /usr/src/arm/linux-2.6.29-pxa950
CROSS_COMPILE ?= /usr/local/arm-marvell-linux-gnueabi/bin/arm-marvell-linux-gnueabi-
ifeq ($(CONFIG_PXA920), y)
EXTRA_CFLAGS += -DPXA920
ifeq ($(KMINORVER), 32)
KERNELDIR ?= /usr/src/arm/linux-2.6.32-pxa920
KERNELDIR ?= /usr/src/arm/linux-2.6.29-pxa920
endif
CROSS_COMPILE ?= /usr/local/arm-marvell-linux-gnueabi/bin/arm-marvell-linux-gnueabi-
else
ifeq ($(KMINORVER),25)
KERNELDIR ?= /usr/src/arm/linux-2.6.25-pxa9xx
CROSS_COMPILE ?= /usr/local/arm/4.1.1/bin/arm-linux-
KERNELDIR ?= /usr/src/arm/linux-2.6.24-pxa9xx
CROSS_COMPILE ?= /usr/local/arm/4.1.1/bin/arm-linux-
endif
endif
endif
endif
ARCH ?= arm
else
ifeq ($(CONFIG MOORESTOWN), y)
ARCH ?= i386
KERNELDIR ?= /usr/src/moorestown/kernel
CROSS_COMPILE ?= /usr/local/i686-unknown-linux-gnu-4.2.1/bin/i686-unknown-linux-gnu-
else
KERNELDIR = /lib/modules/$(shell uname -r)/build
endif
endif
MBT_CHAR_OBJS := mbt_char.o hci_wrapper.o
obj-m := mbtchar.o
mbtchar-objs := $(MBT_CHAR_OBJS)
BINDIR = ../bin_mbtchar
PWD
      := $(shell pwd)
default:
ifeq ($(CONFIG_PXA9XX),
        $(MAKE) -C $(KERNELDIR) M=$(PWD) ARCH=$(ARCH) CROSS_COMPILE=$(CROSS COMPILE) modules
else
ifeq ($(CONFIG_MOORESTOWN),
        $(MAKE) -C $(KERNELDIR) M=$(PWD) ARCH=$(ARCH) CROSS COMPILE=$(CROSS COMPILE) modules
```

Makefile-mbtchar.txt