
INSTALLATION GUIDE

Take the following steps to download and install ZooKeeper:

1. Navigate to <https://zookeeper.apache.org/releases.html> in your web browser and locate the latest stable release.



2. Click the suggested location for the download:

HTTP

<https://dlcdn.apache.org/zookeeper/zookeeper-3.8.6/apache-zookeeper-3.8.6-bin.tar.gz>

3. Extract the contents with in the command line:

```
sudo tar -xvzf <file_name>-bin.tar.gz
```

4. Use the **mv command** to rename the extracted file to *zookeeper* with:

```
sudo mv apache-zookeeper-X.X.X-bin zookeeper [Substituir XXX]
```

5. Navigate to the directory where ZooKeeper is installed. To configure ZooKeeper, create a new configuration file called *zoo.cfg* file in the *zookeeper* directory.

```
cp conf/zoo_sample.cfg conf/zoo.cfg
```

6. Navigate to the directory where ZooKeeper is installed. Start the ZooKeeper service:

```
cd bin; sudo ./zkServer.sh start
```

If successful, the output confirms the ZooKeeper service is running.

Once the ZooKeeper service is running, connect to the ZooKeeper server. To connect to ZooKeeper, run the following command:

```
cd bin; ./zkCli.sh -server 127.0.0.1:2181
```

The command starts the ZooKeeper client and connects to the server running at the specified ip and port. In this case, **127.0.0.1** is the IP address, and **2181** is the default port the ZooKeeper listens on for client connections.

In this example, the output confirms the connection to the ZooKeeper server, as indicated by a new **zk** prompt.

To see a list of available commands, run the following command in the new command prompt:

```
help
```

Close the session with:

```
quit
```

7. To stop the ZooKeeper service, run the command:

```
cd bin; sudo ./zkServer.sh stop
```

JAVA INSTALLATION GUIDE

- `sudo apt update`
- `sudo apt install default-jdk`
- `sudo nano /etc/environment`

1. Add to the following line at the end of the file:

```
JAVA_HOME="/usr/lib/jvm/java-17-openjdk-amd64"
```