

DevArt Gallery for Joomla 6

User Manual v1.0.0

Professional image gallery management for Joomla 6.

1. Introduction

DevArt Gallery is a professional Joomla 6 gallery extension designed for editorial, news, magazine, and high-traffic websites.

It combines modern managed galleries with compatibility support for legacy folder-based gallery archives, allowing both new and existing Joomla websites to maintain a clean and efficient image gallery workflow.

DevArt Gallery was designed with the following goals:

- Clean Joomla 6 native architecture
- Lightweight frontend rendering
- Safe and stable gallery management
- Compatibility with large legacy gallery archives
- Minimal template conflicts
- CDN and cache friendly output
- Production suitability for high-traffic websites

Unlike many generic gallery systems, DevArt Gallery focuses on predictable editorial workflows and path-based gallery portability.

2. System Requirements

Minimum requirements:

- Joomla 6.x
- PHP 8.2+
- GD image library enabled
- Write access to Joomla images directory
- Modern browser for administrator interface

Recommended production environment:

- PHP 8.2 or newer
- SSD hosting
- Cloudflare or another CDN
- Joomla Page Cache where appropriate
- A staging environment for testing updates

3. Installation

Installing DevArt Gallery

1. Download the latest DevArt Gallery package release.
2. In Joomla Administrator, go to:

System → Extensions → Install

3. Upload:

pkg_devartgallery_v1.0.0.zip

4. Wait for the successful installation confirmation.

The package installs:

- DevArt Gallery Component
- DevArt Gallery Frontend Module
- DevArt Gallery Content Plugin
- DevArt Gallery Editor Button Plugin

Post-Installation Checklist

After installation:

- Open **Components → DevArt Gallery**
- Review component Options
- Confirm required plugins are enabled
- Confirm the frontend module is available
- Configure gallery directories if needed

4. Dashboard Overview

The Dashboard is the main control center of DevArt Gallery.

It provides a quick overview of:

- Gallery directories
- Indexed gallery totals
- Managed upload totals
- Scan timestamps
- Upload processing rules
- Plugin and module status
- Frontend publishing status
- Compatibility information

This allows administrators to quickly verify that the gallery environment is healthy and correctly configured.

Dashboard Header Actions

At the top of the Dashboard you will find quick action buttons.

Galleries

This opens the active gallery management screen.

Use this section for:

- Creating new galleries
- Managing active galleries
- Accessing photo management
- Publishing or unpublishing galleries

This is the main day-to-day workflow area.

Galleries Index

This opens the indexing and synchronization screen.

Use this section for:

- Rebuilding the active gallery index
- Rebuilding the legacy gallery index
- Viewing all indexed galleries
- Verifying imported gallery archives

This area is intended mainly for maintenance and synchronization tasks.

New Gallery

This is a direct shortcut for creating a new managed gallery.

Recommended for daily editorial workflows.

Options

This opens Joomla component settings.

Use this section for:

- Active gallery directory configuration
- Legacy gallery directory configuration
- Upload image processing rules
- Watermark settings
- Gallery behavior settings

Dashboard Information Panels

Legacy Archive Directory

Example:

images/galleries1

This folder is intended for imported or historical gallery archives.

Legacy galleries:

- Are indexed for compatibility
- Remain read-only
- Continue supporting historical article shortcodes

Example shortcode:

{gallery}oldgallery{/gallery}

Use this only if you already have existing folder-based gallery archives from older workflows.

For new sites, this may not be needed.

Active Gallery Directory

Example:

images/galleries2

This is the modern managed gallery directory.

New galleries created through DevArt Gallery are stored here.

Active galleries:

- Are fully managed
- Support image uploads
- Support photo management
- Support automatic indexing updates
- Support frontend rendering through module, plugin, and menu integration

Example shortcode:

{gallery}galleries2/my-gallery{/gallery}

This is the recommended workflow for all new galleries.

Indexed Galleries

This panel displays:

- Total indexed galleries
- Active gallery count

- Legacy gallery count

Example:

42 indexed galleries

18 active / 24 legacy

This helps administrators quickly verify indexing status.

If counts appear incorrect after manual folder operations, use Galleries Index tools.

Managed Uploads

This panel displays the total number of managed image records.

Example:

9 managed uploads

This reflects database-managed images for active galleries.

It helps confirm that uploads have been correctly processed.

Last Scans

Displays the most recent index rebuild timestamps.

Example:

Active:

2026-05-13 14:03:35

Legacy:

2026-05-13 13:56:30

Useful when:

- Importing old gallery folders
- Verifying synchronization
- Troubleshooting indexing discrepancies

Future Upload Processing

This panel displays current upload processing rules.

Example:

Max width:

1200px

JPEG quality:

74

Output format:

jpg

Allowed formats:

jpg, jpeg, png, webp

This confirms how newly uploaded images will be processed.

This is especially useful in editorial environments where consistent output size matters.

Plugins / Module Status

Displays current extension status.

This includes:

- Content plugin
- Editor button
- Site module

Example:

ON

If a required extension is OFF, some frontend or editor functionality may not be available.

This provides a quick health check.

Frontend Publishing

Displays available frontend publishing methods.

Includes:

- Menu item support
- Module support

This confirms frontend integration availability.

Examples:

Menu item available

Module available

This helps administrators quickly understand publishing options.

Frontend Delivery

Displays frontend rendering behavior.

Example:

Lazy loading:

ON

Cache safety:

Image version URLs

This confirms cache-friendly frontend behavior.

This is useful for:

- Joomla Page Cache
- Reverse proxies
- Cloudflare
- CDN environments

Legacy vs Active Galleries

Active Galleries

Recommended for all new gallery workflows.

Benefits:

- Full gallery management
- Upload support
- Database tracking
- Portable path-based shortcodes
- Predictable editorial workflow
- Safer frontend integration

This should be your default approach for all modern galleries.

Legacy Galleries

Designed only for compatibility.

Use legacy galleries when:

- Migrating older Joomla sites
- Preserving historical folder archives
- Maintaining previously published article content
- Avoiding large migration work

Legacy galleries are intentionally read-only.

This protects historical archives from accidental modification.

They are not recommended for creating new galleries.



Best Practice Recommendation

For new Joomla installations:

Use only Active Galleries.

Enable Legacy support only when you already have an existing archive that must continue working.

This provides the cleanest, safest, and most maintainable workflow.



Galleries Index

The Galleries Index section is the synchronization and compatibility management area of DevArt Gallery.

This screen maintains the internal gallery index database used by the component to track both modern active galleries and legacy folder-based archives.

Unlike the main Galleries section, this area is intended primarily for maintenance, synchronization, migration workflows, and troubleshooting.

Normal day-to-day gallery creation and image uploads do not usually require access to this screen.

Use Galleries Index when you need to:

- Rebuild active gallery indexing
- Rebuild legacy archive indexing
- Validate imported gallery folders
- Troubleshoot missing galleries
- Verify gallery synchronization
- Audit active and legacy gallery status

Header Actions

Rebuild Active Index

This action rebuilds the internal index for active managed galleries.

Use this when:

- gallery folders were modified manually outside the component
- active galleries appear out of sync
- imported gallery structures need verification
- troubleshooting index inconsistencies

Under normal use, active galleries update automatically during standard component operations such as gallery creation, uploads, and managed changes.

Frequent rebuilding should not normally be necessary.

Rebuild Legacy Index

This action scans the configured legacy archive directory and rebuilds the compatibility index.

Use this when:

- importing old gallery archives
- restoring legacy gallery backups
- manually adding historical gallery folders
- verifying migration compatibility

Legacy archives can contain a large number of folders and images.

For this reason, rebuilding may take noticeable time on large installations.

This operation should only be used when legacy archive contents actually change.

Legacy Warning Notice

A warning message is displayed when viewing the Galleries Index screen.

This is intentional.

Legacy archive rebuilding may scan very large numbers of folders and images, especially on long-running editorial websites with historical gallery archives.

The warning exists to remind administrators that rebuild operations may be resource-intensive.

Search & Filters

The Galleries Index section includes filtering tools to help administrators audit large gallery collections efficiently.

Status	Gallery	Type	Images	Path	Shortcode
✓	voyager160411	active	19	images/galleries2/voyager160411	{gallery}galleries2/voyager160411{/gallery}
✓	testgallery	active	6	images/galleries2/testgallery	{gallery}galleries2/testgallery{/gallery}
✓	test5	active	1	images/galleries2/test5	{gallery}galleries2/test5{/gallery}

Galleries

The Galleries section is the primary management area for active DevArt Gallery collections.

This is where administrators create, manage, publish, and maintain modern galleries intended for normal day-to-day use.

Unlike legacy galleries, active galleries are fully managed by the component and support image uploads, photo management, publishing control, and automatic frontend integration.

This section is intended for regular editorial and administrator workflows.

Use the Galleries section to:

- Create new galleries

- Manage active galleries
- Search existing galleries
- Filter gallery listings
- Sort gallery collections
- Publish or unpublish galleries
- Delete galleries
- Access photo management
- Copy article shortcode references

For most users, this will be the main working area of DevArt Gallery.

Header Actions

New Gallery

Creates a new managed active gallery.

Use this when creating a gallery for:

- Joomla articles
- homepage content
- category pages
- frontend modules
- menu-based gallery pages

New galleries are stored inside the configured Active Gallery Directory.

Example:

images/galleries2/

This is the recommended workflow for all new gallery creation.

Galleries Index

Opens the synchronization and indexing interface.

Use this section only when needed for:

- rebuilding indexes
- verifying imported galleries
- validating synchronization
- maintaining legacy archive compatibility

Normal gallery work does not usually require this section.

Dashboard

Returns directly to the DevArt Gallery Dashboard.

Search & Filters

The Galleries screen includes filtering tools for easier management of larger gallery collections.

These tools help administrators locate galleries quickly and maintain performance in larger installations.

Legacy Galleries Inside This Screen

Legacy galleries may also appear in the listing for compatibility visibility.

Important:

Legacy galleries are read-only.

They are intended only for compatibility with historical archives.

They should not be treated as normal managed galleries.

For all new work, always use Active galleries.

Best Practice


For modern Joomla workflows:

Use Active galleries only.

This provides:

- full image management
- upload support
- publishing control
- automatic indexing
- predictable frontend behavior
- safer maintenance

Legacy galleries should remain compatibility-only unless older archives must be preserved.



Creating and Managing Gallery Photos

Once an active gallery has been created, DevArt Gallery provides a complete management interface for uploading, organizing, and maintaining images.

This is the main operational workflow for adding content to a gallery.

To access this screen:

Components → DevArt Gallery → Galleries → Manage Photos

Each active gallery has its own dedicated photo management area.

Gallery Overview

At the top of the screen you will see the selected gallery name.

Example:

000test

You will also find a shortcut button:

Back to Galleries

This returns to the main gallery listing.

Adding New Photos

The Add Photos section is the primary upload interface.

Supported source formats:

- JPG
- JPEG

- PNG
- WEBP

Upload workflow:

1. Click **Select Photos**
2. Choose one or multiple image files
3. Click **Add & Process**

The component will automatically process the images according to the current gallery settings.

Automatic Processing

Uploaded images are automatically optimized.

Depending on configuration, processing may include:

- resizing oversized images
- converting images to JPG output
- applying compression
- applying watermark overlays (if enabled)

Example configuration:

- Maximum width: 1200px
- JPEG quality: 74
- Output format: JPG

This ensures consistent frontend image delivery.

Upload Guidelines

The upload panel displays current processing rules.

This allows administrators to immediately verify:

- allowed file types
- output behavior
- resizing rules

Example:

Allowed source files:

jpg, jpeg, png, webp

Images wider than 1200px are resized before storage.

This keeps gallery images lightweight and consistent.

Multiple Uploads

Multiple images can be uploaded in a single operation.

This is recommended for editorial workflows where galleries are built quickly from multiple photos. The component processes all selected images automatically.

Scan Existing Photos

The **Scan Existing Photos** tool imports image files already present inside the gallery folder.

Use this when:

- files were uploaded manually via FTP
- files were copied from backups
- images already exist in the filesystem but are missing from the database

Important:

This operation does NOT:

- move files
- rename files
- recompress files
- overwrite files

It only registers existing image files into the gallery database.

This makes it safe for migration and recovery workflows.

Watermark Settings

Each active gallery can optionally apply watermark processing to future uploads.

This is controlled per gallery.

Enable:

Add watermark to future uploads in this gallery

When enabled, newly uploaded images will receive watermark processing.

Important:

Existing images are NOT reprocessed automatically.

Only future uploads are affected.

Watermark Configuration

When watermark mode is enabled, additional settings become available.

These include:

Watermark File

Select the watermark image.

Recommended format:

PNG with transparency

Use a clean transparent PNG logo or branding mark.

Watermark Position

Available positions allow placement control.

Example:

- Bottom right
- Bottom left
- Top right
- Top left
- Center

Choose the placement that best matches your visual workflow.

Bottom right is commonly recommended.

Watermark Width (%)

Controls relative watermark size.

Example:

18%

This scales the watermark relative to image dimensions.

Smaller values create subtle branding.

Larger values create stronger visibility.

Watermark Opacity

Controls transparency.

Example:

70

Lower values:

more transparent

Higher values:

more visible

Recommended editorial range:

50–80

Watermark Margin

Controls spacing from image edges.

Example:

24

Higher values move the watermark further inward.

Useful for avoiding cropping conflicts.

Save Gallery Settings

After changing watermark settings:

click **Save Gallery Settings**

Settings apply to future uploads only.

Gallery Information Panel

The gallery information block displays useful operational details.

Gallery Name

Example:

000test

The internal gallery identifier.

Gallery Path

Example:

galleries2/000test

This is the filesystem location for the managed gallery.

Useful for:

- troubleshooting
- FTP verification
- migration workflows

Gallery Shortcode

Example:

```
{gallery}galleries2/000test{/gallery}
```

This shortcode can be copied directly into:

- Joomla articles

- custom HTML modules
- supported content areas

CMS Content Integration

A quick reminder panel explains frontend usage.

Basic workflow:

1. Copy the shortcode
2. Paste into Joomla content
3. Save the article

The gallery will render automatically via the content plugin.

Image Management Grid

The lower section displays all images currently registered in the gallery.

This provides:

- image previews
- file names
- selection checkboxes
- pagination controls
- bulk deletion

Delete Selected Photos

Bulk deletion removes selected managed images.

Use this carefully.

Deleting photos removes them from:

- gallery display
- managed image records

Recommended workflow:

review selected images carefully before deletion.

Best Practice Workflow

Recommended modern workflow:

1. Create a new active gallery
2. Upload optimized source images
3. Enable watermarking if needed
4. Save gallery settings
5. Verify image processing


6. Copy shortcode
7. Insert into Joomla content
8. Publish



Migration Workflow

If files already exist manually:

1. create the gallery
2. upload files via FTP if needed
3. use **Scan Existing Photos**
4. verify imported images
5. publish

This is especially useful for migration projects.





Inserting a Gallery into a Joomla Article

DevArt Gallery includes native Joomla content integration, allowing galleries to be inserted directly inside Joomla articles using the content plugin.

This makes it easy for editors to place image galleries anywhere within article content without writing complex code.

Galleries can be inserted:

- inside Joomla articles
- inside supported content areas
- inside compatible custom content workflows

The frontend gallery is rendered automatically by the DevArt Gallery content plugin.

Method 1: Using the DevArt Gallery Editor Button (Recommended)

This is the easiest and recommended method for editors.

Open your Joomla article:

Content → **Articles** → **New or Edit Article**

Inside the editor toolbar:

CMS Content → **DevArt Gallery**

Click the DevArt Gallery editor button.

A gallery selection popup will appear.

Gallery Selection Popup

The popup displays indexed galleries available for insertion.

Each entry shows:

- gallery name
- gallery type
- gallery path
- image count
- shortcode preview

Example:

Gallery:

000test

Type:

active

Path:

galleries2/000test

Images:

9

Shortcode:

```
{gallery}galleries2/000test{/gallery}
```

Search

The popup includes a search field.

Use it to quickly locate galleries by:

- gallery name
- gallery path

Example:

000test

This is useful on installations with many galleries.

Insert

Click:

Insert

The shortcode is automatically inserted into the article editor.

Example:

```
{gallery}galleries2/000test{/gallery}
```

No manual typing is required.

This reduces editorial mistakes and speeds up publishing workflows.

Article Placement

The shortcode can be inserted anywhere inside article content.

Examples:

- between paragraphs
- after article introductions
- before article conclusions
- between content sections
- in gallery-heavy editorial layouts

Example:

Intro text

```
{gallery}galleries2/000test{/gallery}
```

Additional article content

The gallery will render in that exact location on the frontend.

Method 2: Manual Shortcode Insertion

Advanced users may insert shortcodes manually.

Example for active galleries:

```
{gallery}galleries2/000test{/gallery}
```

Example for legacy galleries:

```
{gallery}oldgallery{/gallery}
```

Manual insertion may be useful when:

- copying content between sites
- migration workflows
- bulk editorial operations
- importing archived article content

Frontend Rendering

When the article is viewed on the frontend, the shortcode is automatically replaced with the gallery output.

The gallery will display using the configured frontend layout.

Features include:

- responsive gallery output
- lightweight rendering
- popup viewer support (if enabled)
- lazy loading support
- cache-friendly image URLs

This keeps frontend delivery efficient.

Multiple Galleries in One Article

DevArt Gallery supports multiple gallery insertions inside a single article.

Example:

Article intro

```
{gallery}galleries2/event-gallery{/gallery}
```

Additional article text

```
{gallery}galleries2/behind-scenes{/gallery}
```

Conclusion

Each gallery renders independently.

This is useful for long-form editorial or feature content.

Legacy Gallery Compatibility

Older gallery archives can also be inserted.

Example:

```
{gallery}ubuntu{/gallery}
```

This preserves compatibility with historical article content.

Legacy galleries are rendered through the same content plugin.

Important:

Legacy galleries are compatibility-only and should not be used for new editorial workflows unless older content requires them.

Publishing Requirements

For article galleries to display correctly:

The DevArt Gallery content plugin must be enabled.

Verify:

System → Plugins → Content - DevArt Gallery

Status:

Published

If disabled, shortcodes will appear as raw text instead of rendering galleries.

Troubleshooting

Shortcode appears as plain text

Cause:

Content plugin disabled.

Fix:

Enable:

Content - DevArt Gallery

Gallery does not appear

Check:

- gallery is published
- shortcode path is correct
- content plugin is enabled
- article cache has been cleared if necessary

Popup viewer does not open

Check:


- popup support is enabled in the relevant frontend configuration
- template JavaScript conflicts
- frontend cache state

Best Practice

Recommended editorial workflow:

1. Create gallery
2. Upload images
3. Verify frontend-ready state
4. Open article editor
5. Use CMS Content → DevArt Gallery
6. Select gallery
7. Insert shortcode
8. Save article
9. Preview frontend rendering

This is the safest and fastest workflow for daily publishing.



DevArt Gallery

Insert a path-based gallery shortcode.

Select an indexed gallery. The shortcode will be inserted as {gallery}path{/gallery}.

Search

{gallery}galleries2/extix165{/gallery}

antix16

active galleries2/antix16 27 images

{gallery}galleries2/antix16{/gallery}

Insert

antergos20161120

active galleries2/antergos20161120 23 images

{gallery}galleries2/antergos20161120{/gallery}

Insert

000test

active galleries2/000test 9 images

{gallery}galleries2/000test{/gallery}

Insert

xubuntu16041

legacy xubuntu16041 17 images

{gallery}xubuntu16041{/gallery}

Insert

ubuntustudio16041

Prev

JPAGE 1 of 3 - 42 items

Next

Article Text

Edit Insert View Format Table Tools

CMS Content B I U S Paragraph Paragraph System Font 16px

test intro text Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua.

{gallery}galleries2/000test{/gallery}

Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat. Duis aute irure dolor in reprehenderit in voluptate velit esse cillum dolore eu fugiat nulla pariatur. Excepteur sint occaecat cupidatat non proident, sunt in culpa qui officia deserunt mollit anim id est laborum.



p

75 words

Toggle Editor



test intro text Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua.



Frontend Publishing with Module and Menu Items

DevArt Gallery supports frontend publishing through both Joomla modules and Joomla menu items.

This allows galleries to be displayed outside article content, making them suitable for homepage placements, sidebar blocks, landing pages, and dedicated gallery pages.

Supported frontend publishing methods:

- Joomla articles (via shortcode)
- Joomla frontend module
- Joomla menu item pages

This gives administrators flexible publishing options depending on site structure.

Using the DevArt Gallery Module

The frontend module allows a selected gallery to be displayed inside any Joomla module position.

This is useful for:

- homepage gallery blocks
- sidebar galleries
- category landing pages
- footer galleries
- custom template positions

Creating a Module

Go to:

Content → **Site Modules** → **New**

Select:

DevArt Image Gallery

This opens the module configuration screen.

Module Configuration

Title

Set the module title.

Example:

DevArt Image Gallery

You may choose whether the title is shown on the frontend.

Select Indexed Gallery

Choose the gallery to display.

The selector shows:

- gallery name
- gallery path
- gallery type
- image count

Example:

000test — galleries2/000test — ACTIVE — 9 images

Only indexed galleries appear here.

Layout

Available layouts:

- Normal grid
- Masonry

Normal Grid

Displays a clean uniform gallery layout.

Recommended for:

- most editorial websites

- balanced layouts
- predictable frontend rendering

Masonry

Displays a dynamic masonry-style gallery.

Recommended for:

- visual-heavy galleries
- image-driven landing pages
- magazine-style layouts

This creates a more fluid presentation.

Image Limit

Controls how many images are shown.

Examples:

0 = show all images

6 = show only first 6 images

12 = show first 12 images

Useful for homepage teaser galleries.

Image Order

Controls frontend image ordering.

Examples:

- gallery ordering
- filename ordering

Use this when a specific presentation sequence is required.


Position

Choose the Joomla module position.

Examples:

- sidebar
- homepage-top
- footer
- custom template positions

Available positions depend on your Joomla template.



Using DevArt Gallery as a Joomla Menu Item

DevArt Gallery also supports native Joomla menu item integration.

This creates a dedicated frontend gallery page.

Useful for:

- standalone gallery pages
- gallery landing pages
- permanent navigation entries
- public image archive pages

Creating a Menu Item

Go to:

Menus → Your Menu → New

For Menu Item Type:

click **Select**

Choose:

DevArt Gallery

This creates a gallery-based Joomla menu item.

Menu Item Configuration

Title

Set the frontend menu title.

Example:

Test Gallery

This is what visitors will see in navigation.

Select Gallery

Choose the indexed gallery to display.

The selector shows:

- gallery name
- gallery path
- gallery type
- image count

Example:

000test — galleries2/000test — ACTIVE — 9 images

Menu Settings

All normal Joomla menu settings remain available.

Examples:

- menu placement
- parent menu
- ordering
- access
- template style
- metadata

This means DevArt Gallery integrates cleanly with standard Joomla navigation workflows.

Frontend Behavior

When visitors open the menu item, the selected gallery is rendered as a full frontend page.

Behavior includes:

- responsive gallery output
- frontend image display
- popup viewer support (if enabled)

- lazy loading
- lightweight rendering
- cache-friendly output

This makes menu items ideal for public gallery pages.

Module vs Menu: When to Use Each

Use Module When

You need:

- gallery blocks inside existing pages
- homepage sections
- sidebar placement
- embedded visual content
- smaller gallery previews

Use Menu Item When

You need:

- full standalone gallery pages
- navigation-linked galleries
- dedicated archive pages
- permanent public gallery destinations

The screenshot displays the 'Menus: Edit Item' interface. At the top, there's a dark header with the 'art' logo, the title 'Menus: Edit Item', version '6.1.0', and a 'Clean Cache' button. Below the header is a toolbar with 'Save', 'Save & Close', and 'Close' buttons, along with 'Toggle Inline Help' and 'Help' links. The main form area has tabs for 'Details', 'Display', 'Link Type', 'Page Display', 'Metadata', 'Gantry Menu', and 'Module Assignment'. The 'Details' tab is selected, showing a form with the following fields:

- Title ***: test gallery
- Alias**: testgallery
- Menu Item Type ***: DevArt Gallery (with a 'Select' button)
- Select Gallery ***: A dropdown menu showing a list of galleries:
 - 000test – galleries2/000test – ACTIVE – 9 images
 - 000test – galleries2/000test – ACTIVE – 9 images
 - antergos20161120 – galleries2/antergos20161120 – ACTIVE – 23 images
 - antix16 – galleries2/antix16 – ACTIVE – 27 images
 - extix165 – galleries2/extix165 – ACTIVE – 22 images
 - handylinux25 – galleries2/handylinux25 – ACTIVE – 22 images
 - kaos201611 – galleries2/kaos201611 – ACTIVE – 24 images
 - knoppix761 – galleries2/knoppix761 – ACTIVE – 16 images
- Link**: (empty)
- Target Window**: (empty)
- Template Style**: (empty)
- Menu ***: Main Menu (dropdown)
- Parent Item**: - No parent - (dropdown)
- Ordering**: test gallery (dropdown)
- Status**: Published (dropdown with a green checkmark)
- Default Page**: No (checkbox)
- Start Publishing**: (checkbox)

Component Options

DevArt Gallery includes a comprehensive Joomla options panel for configuring gallery behavior, upload processing, frontend display, migration compatibility, uninstall handling, and administrator permissions.

To access component options:

Components → DevArt Gallery → Options

or

System → Global Configuration → DevArt Gallery

These settings control the default behavior of the component.

Paths & Migration

This section controls gallery storage locations and migration compatibility.

Legacy / Active Indexing Rule

DevArt Gallery scans only first-level folders inside the configured base directories.

This prevents:

- duplicate indexing
- nested gallery confusion
- accidental recursive archive scanning

Nested folders are intentionally ignored.

This keeps indexing predictable and stable.

Legacy Archive Directory

Defines the location used for older gallery archives.

Example:

images/galleries1

Used for:

- historical gallery migrations
- legacy shortcode compatibility
- existing archive preservation

Example legacy shortcode:

{gallery}oldgallery{/gallery}

Important:

This directory is intended for older imported galleries.

New gallery creation should normally not use the legacy archive location.

Active Gallery Directory

Defines the folder used for managed galleries.

Example:

images/galleries2

All newly created galleries use this location by default.

Example active shortcode:

```
{gallery}galleries2/my-gallery{/gallery}
```

Recommended:

keep active galleries separate from legacy archives.

This improves migration clarity and long-term maintenance.

Path Helper

The path helper guidance explains folder requirements.

Rules include:

- relative paths only
- no leading slash
- no unsafe filesystem paths
- automatic path normalization

Examples:

Valid:

images/galleries

Invalid:

/images/galleries

This improves filesystem safety.

Frontend Display

Controls the global frontend gallery appearance.

Desktop Columns

Sets gallery columns for desktop screens.

Example:

4

Recommended range:

3–6

Higher values create denser grids.

Tablet Columns

Sets tablet layout columns.

Example:

3

Recommended:

2–4

Mobile Columns

Sets mobile layout columns.

Example:

2

Recommended:

1–2

This ensures responsive frontend behavior.

Frontend Mode

Controls default gallery layout.

Available modes:

- Normal Grid
- Masonry

Normal Grid

Uniform image blocks.

Recommended for:

- editorial websites
- predictable layouts
- clean visual presentation

Masonry

Variable-height flowing layout.

Recommended for:

- visual portfolios
- magazine-style galleries
- mixed image aspect ratios

Show Captions

Displays image captions when available.

Options:

Yes / No

Enable if caption text should appear beneath images.

Disable for cleaner visual layouts.

Enable Popup

Controls frontend popup viewer behavior.

Options:

Yes / No

Enabled:

images open in popup overlay

Disabled:

images open directly in browser tabs

Recommended:

Enabled

Lazy Loading

Uses native browser lazy loading.

Options:

Yes / No

Benefits:

- faster initial page load
- reduced bandwidth usage
- improved frontend performance

Recommended:

Enabled

Image Spacing

Controls grid spacing.

Example:

12

Measured in pixels.

Lower values:

tighter layouts

Higher values:

more visual spacing

Image Radius

Controls corner rounding.

Example:

10

Measured in pixels.

Set to:

0

for square corners.

Hover Effect

Enables subtle frontend hover animation.

Options:

Yes / No

Recommended:

Enabled

for improved visual feedback.

Upload Processing

Controls image upload behavior.

Strict Latin Filename / Folder Policy

Enforces safe filename generation.

Options:

Yes / No

When enabled:

generated names use only:

- lowercase Latin letters
- numbers
- dashes
- underscores

Spaces and unsafe characters are excluded.

Recommended:

Enabled

Especially for production and migration workflows.

Maximum Width

Maximum width for uploaded images.

Example:

1200

Measured in pixels.

Oversized images are resized automatically.

This helps optimize frontend performance.

JPG Quality

Compression level for JPG output.

Example:

74

Range:

50–100

Lower values:

smaller file sizes

Higher values:

better image quality

Recommended editorial range:

70–80

WebP Quality

Compression level for WebP output.

Example:

78

Used when WebP output format is selected.

Recommended range:

70–85

Output Format

Defines default processed image format.

Options:

- JPG
- WebP

JPG:

best compatibility

WebP:

smaller file sizes, modern optimization

Recommended:

JPG for broad compatibility

WebP for optimization-focused deployments

Max Upload Size

Maximum file size per uploaded image.

Example:

8 MB

Used as a safety control.

Helps prevent oversized uploads.

Max Images Per Gallery

Limits managed gallery size.

Example:

120

Protects administrator workflows from excessive uploads.

Useful for:

- editorial consistency
- performance protection
- operational safety

Uninstall

Controls uninstall data retention.

Keep Data on Uninstall

Options:

Yes / No

When enabled:

DevArt Gallery preserves:

- gallery database tables
- image records
- gallery index data
- component settings

When disabled:

component data is removed during uninstall.

Recommended:

No

for clean removal.

Use Yes when preserving data for reinstall or migration.

Permissions

DevArt Gallery supports Joomla native ACL permissions.

Available permissions include:

- Configure ACL & Options
- Configure Options
- Access Administration Interface
- Create
- Delete
- Edit
- Edit State
- Edit Own

This allows integration with Joomla administrator role workflows.

DevArt Image Gallery: Options

6.1.0

Take a Tour

User Menu

Clean Cache

SaveSave & CloseClose

Help

System

Global Configuration

Component

Admin Tools for Joomla!

Articles

Banners

Cache

Check-in

Contacts

DevArt Article Photo

DevArt Exts

DevArt Gallery

DevArt Social Cards

DevArt Utils

Gantry 5 Themes

Guided Tours

Installer

Joomla! Update

Languages

Paths & Migration

Frontend Display

Upload Processing

Uninstall

Permissions

Paths & Migration

Legacy / Active indexing rule

Legacy Archive Directory

Active Gallery Directory

Path helper

Legacy and Active scans index only first-level folders inside the selected base directory. Nested folders are ignored to avoid duplicate galleries during migrations.

images/galleries1

Old gallery folder used by legacy shortcodes. Relative path from Joomla root, without leading slash. Example: images/galleries

images/galleries2

New managed gallery folder. Future uploads use this directory by default. Relative path from Joomla root, without leading slash. Example: images/galleries2

Use Joomla Media to create/select folders, then paste the relative folder path here. Paths are normalized automatically: leading and trailing slashes are removed, duplicate slashes are collapsed, and unsafe paths are blocked.

SaveSave & CloseClose

Help

System

Global Configuration

Component

Admin Tools for Joomla!

Articles

Banners

Cache

Check-in

Contacts

DevArt Article Photo

DevArt Exts

DevArt Gallery

DevArt Social Cards

DevArt Utils

Gantry 5 Themes

Guided Tours

Installer

Joomla! Update

Languages

Mail Templates

Media

Menus

Messaging

Modules

Multilingual Associations

News Feeds

Plugins

Post-installation Messages

Privacy

Redirects

Scheduled Tasks

Smart Search

Tags

Templates

User Actions Log

Paths & Migration

Frontend Display

Upload Processing

Uninstall

Permissions

Frontend Display

Desktop Columns

Tablet Columns

Mobile Columns

Frontend Mode

Show Captions

Enable Popup

Lazy Loading

Image Spacing

Image Radius

Hover Effect

4

Number of frontend gallery columns on desktop screens.

3

Number of frontend gallery columns on tablet screens.

2

Number of frontend gallery columns on mobile screens.

Normal grid

Normal uses a stable equal-height grid. Masonry uses lightweight CSS columns for variable-height image flow. This is a global article display setting; shortcode-level layout overrides are disabled for stability.

No

Show image captions on the frontend when captions exist.

Yes

Use a tiny vanilla JavaScript popup. When disabled, images open directly in a new tab.

Yes

Add native browser loading=lazy to gallery images.

12

Grid gap in pixels.

10

Frontend image corner radius in pixels.

Yes

Add a subtle frontend hover animation.

SaveSave & CloseClose

Help

System

Global Configuration

Component

Admin Tools for Joomla!

Articles

Banners

Cache

Check-in

Contacts

DevArt Article Photo

DevArt Exts

DevArt Gallery

DevArt Social Cards

DevArt Utils

Gantry 5 Themes

Guided Tours

Installer

Joomla! Update

Languages

Mail Templates

Media

Menus

Messaging

Modules

Multilingual Associations

News Feeds

Plugins

Post-installation Messages

Privacy

URL

Redirects

Paths & Migration

Frontend Display

Upload Processing

Uninstall

Permissions

Upload Processing

Filename policy

Managed gallery uploads are renamed automatically using the gallery folder as prefix plus numbering, for example my-gallery-001.jpg or my-gallery-001.webp. The extension follows the selected output format.

Strict Latin filename / folder policy

Yes

When enabled, generated gallery folders and processed upload filenames use only lowercase Latin letters, numbers, dashes and underscores, without spaces. Recommended for production and migrations.

Maximum Width

1200

Maximum width for uploaded images (px)

JPG Quality

74

JPG compression quality (50-100)

WebP Quality

78

Default WebP quality when Output Format is set to WebP.

Output Format

JPG

Default format for uploaded images

Max Upload Size

8

Maximum upload size per image (MB)

Max Images Per Gallery

120

Safety limit for how many images can be stored in one managed gallery.

SaveSave & CloseClose

Help

System

Global Configuration

Component

Admin Tools for Joomla!

Articles

Banners

Cache

Check-in

Contacts

Paths & Migration

Frontend Display

Upload Processing

Uninstall

Permissions

Uninstall

Keep Data on Uninstall

Yes

When enabled, DevArt Gallery keeps gallery tables, image records, index data, and component settings during uninstall. Default is No for a clean uninstall.

Save

Save & Close

Close

Help

System

> Global Configuration

Component

> ~~Submenu Placeholder for Joomla!~~

> Articles

> Banners

> Cache

> Check-in

> Contacts

> DevArt Article Photo

> DevArt Exts

> DevArt Gallery

> DevArt Social Cards

> DevArt Utils

> Gantry 5 Themes

> Guided Tours

> Installer

> Joomla! Update

> Languages

> Mail Templates

> Media

> Menus

> Messaging

> Modules

> Multilingual Associations

> News Feeds

> Plugins

p?option=com_config Installation Messages

Paths & Migration

Frontend Display

Upload Processing

Uninstall

Permissions

Permissions

Expand for notes about setting the permissions.

Public

- Guest

- Manager

- Administrator

- Registered

- Author

- Editor

- Publisher

- Super Users

Action

Select New Setting

Calculated Setting

Configure ACL & Options

Inherited

Not Allowed (Inherited)

Configure Options

Inherited

Not Allowed (Inherited)

Access Administration Interface

Inherited

Not Allowed (Inherited)

Create

Inherited

Not Allowed (Inherited)

Delete

Inherited

Not Allowed (Inherited)

Edit

Inherited

Not Allowed (Inherited)

Edit State

Inherited

Not Allowed (Inherited)

Edit Own

Inherited

Not Allowed (Inherited)