

ONE-HANDED KEYBOARD CHEAT SHEET

Hyn (Halmak) Mode • Spacebar Mirror • Left-Hand Accessibility Layout

TOGGLE: [Tab + Q] (Hyn Mode Only)

1. BASE LAYER (HYN / HALMAK) - DEFAULT

Q c	W s	E t	R h	T r
A a	S e	D i	F o	G u
Z l	X d	C n	V m	B NVDA

2. MIRROR LAYER (HOLD SPACEBAR)

Q z	W b	E p	R y	T x
A q	S g	D w	F f	G v
Z c	X b	C k	V j	B Win+H

3. MOUSE NAVIGATION MODE (TAP L-CTRL)

W / A / S / D	Move Cursor Up / Left / Down / Right (Accelerating)
Q / E	Mouse Wheel Up / Down (Scroll)
CapsLock	Left Click (Hold to Drag)
Left Shift	Right Click
Space + CapsLock	Send Enter
Space + Shift	Right Click (Fixed)
Q + W / W + E	Home / End (Quick Jump)

4. NAVIGATION & EDITING CHORDS

W + E	Up Arrow	A + F	Ctrl + C (Copy)
S + D	Down Arrow	A + F (Mirror)	Ctrl + V (Paste)
A + S	Left Arrow	Z + X	Ctrl + Z (Undo)
D + F	Right Arrow	C + V	Ctrl + Y (Redo)
Q + W	Home	S + F	Backspace
E + R	End	S + D + F	Ctrl + Backspace
A + D	Delete	X + C	Ctrl + J

5. PUNCTUATION & SYMBOLS

S + E	/ (Slash)	S + E (Mir)	\ (Backslash)
G + R	? (Question)	G + R (Mir)	(Pipe)
A + G	@ (At sign)	W + T (Mir)	] (Close Bracket)
Q + R	{ (Open Brace)	Q + R (Mir)	} (Close Brace)
S + G	((Open Paren)	S + G (Mir)	) (Close Paren)
W + T	[(Open Bracket)	F + E (Mir)	: (Colon)
A + W	" (Double Quote)	A + W (Mir)	' (Single Quote)
S+E+F	= (Equals)	S+E+F (Mir)	+ (Plus)

6. MEDIA, BRIGHTNESS & UTILITIES

A + R	Volume Up	G + E	Seek Forward (5s)
Q + F	Volume Down	G + W	Seek Rewind (5s)
G + T	Play / Pause	A + T	Brightness Up
Q + T	Screen Capture (PrtScn)	Q + G	Brightness Down
Z+X+C+V	F10 Key	W+E+R	. (Period)
R + W	, (Comma)	F + E	; (Semicolon)
Q + E	< (Less Than)	E + T	> (Greater Than)
F + G	_ (Underscore)	F + G (Mir)	- (Hyphen / Minus)

7. CORE MODIFIERS & LAYER WORKFLOW

SPACEBAR (Thumb)

- Tap: Types standard Space
- Hold: Activates Mirror Layer
- Hold Space + B: Win + H (Dictation)
- Hold Space + 1..0: 0..1 (Reversed numbers)

LEFT CONTROL

- Tap: Toggle Mouse Navigation Mode ON / OFF
- Hold: Activates Control Layer (Helper shortcuts)
- Hold Ctrl + Space: Mirror shortcut chords

LEFT WINDOWS (Win)

- Tap: Normal Windows Start Key
- Hold: Activates Fn Layer
- Hold Win + Space: Switch back to QWERTY mode

PHYSICAL 'B' KEY

- In Hyn Mode: Toggle [NVDA] (Admin)
- In Mirror Layer (Space + B): Sends [Win + H]
- In QWERTY Mode: Standard [b] key

CONTROLS: Toggle: [Tab + Q] | Zoom: Mouse Wheel (up to 6X) | Pan: Hold Middle Mouse Button & Drag | Close: Left/Right Click or Any Key