❓ Frequently Asked Questions (FAQ) for VOICE Streaming

1. How can a Voice Bot Platform integrate with our platform for Two-Way Audio Streaming?

Integration is straightforward.
We provide a **"Bi-Directional Audio Streaming Integration Document"** that outlines the WebSocket event structure required for successful integration.
Your Voice Bot platform must adhere to our event format and standards to establish Two-Way Audio Streaming for incoming call flows.

---

2. What information is required from the Voice Bot Platform for setup?

To configure your Voice Bot with our platform (during Beta):

- Go to **Channels Hub → VOICE Bot Section → Add VOICE Bot**
- Provide the following details:
  - **Bot Name** for identification.
  - Description
  - **WSS URL** where our platform will stream the audio and receive the bot's responses.

---

3. How is VOICE Streaming secured?

VOICE Streaming leverages **WSS (WebSocket Secure)** connections for encrypted, real-time audio transfer.
WSS is the secure version of WebSocket protocol, built on top of TLS (Transport Layer Security), ensuring that both the audio streams and metadata exchanged are encrypted and protected from eavesdropping, tampering, and man-in-the-middle attacks.

Your streaming sessions are fully safeguarded, adhering to industry best practices in security.

---

4. Where can we view the CDR (Call Detail Records) for VOICE Streaming?

Starting from the Beta phase, **Call Detail Records (CDRs)** for both **Incoming** and **Outgoing** calls using VOICE Streaming are available. These are visible in the **Call Logs** section and include details like:

- Call Duration
- Bot Name
- Transfer (if applicable)

---

5. Can a Voice Bot transfer the call to a live agent?

Yes. From the **Beta Phase onwards**, we support **Call Transfer to Agent, IVR and Department** using the **Call Operations API** on UIX.
👉 This feature currently supports only **Incoming Calls** streamed to the VOICE Bot.

---

6. Which call types are supported in the Beta release?

- ✅ **Incoming Calls** via **UIX (Unified Interactions Experience)**
- ✅ **Outgoing Calls** initiated using the **Click to Call Support API**
- ❌ **Broadcast/Outreach Campaigns** are not yet supported and will be added in a future release.

---

7. Can we configure multiple Voice Bots for different DIDs?

Yes, in the Alpha phase (through backend support), we can configure **different bots** against **different DIDs**.
This allows customers to route specific call flows to distinct bots based on the dialed number.

---

8. Will Voice Bot responses have a playback delay?

In Alpha:

- VOICE Streaming aims for **near real-time** interaction (~sub-second delay).
- Minor latency might be introduced due to network conditions and bot response processing.
- Performance optimization and further latency reduction are targeted in upcoming Beta and GA (General Availability) phases.

---

9. How can a VOICE Bot end the call after the interaction is complete?

The **VOICE Bot Platform** can invoke the **Hangup API** using the `callSid` received in the `start` event during VOICE Streaming to programmatically disconnect the call.

---

10. The Click to Call Support API is taking too long to respond. How can this be improved?

You can improve response times by passing the optional body parameter:
`async=1`

- This will give an **immediate acknowledgment** (without waiting for call status).
- You won't receive a `call_id` in the response, but you can track the interaction using up to **three custom parameters** you pass in the API call. These parameters will appear in both:
  - Call Webhooks
  - `start` event of VOICE Streaming

---

11. How can VOICE Streaming be configured for an Incoming Call?

To configure:

1. Go to **Channels Hub → VOICE Bot Section**
2. Add your VOICE Bot with required details (as per Q2)
3. Navigate to **My Numbers → Configure Destination**
4. Select the VOICE Bot for the DID

This setup will enable VOICE Streaming for that DID on Incoming Calls.

---

12. How can VOICE Streaming be configured for an Outgoing Call using the Click to Call Support API?

To configure:

1. Go to **Channels Hub → VOICE Bot Section**
2. Add your VOICE Bot with required details (as per Q2)
3. Navigate to **API Connect → Click to Call Support API → Generate API Key**
4. Set the **VOICE Bot as the destination** for the API Key.

This setup allows VOICE Streaming to be triggered for outgoing calls using the specified API Key.
