

Invoice #1213709

Created: September 28, 2021 Payment Terms: Net 30

P.O. # 1249797

Bill To:

HITEC POWER PROTECTION Lianne van Borssum Waalkes Bedrijvenpark Twente no. 40 7602 KB, NETHERLANDS

Ship To:

Hitec Power Protection Lianne van Borssum Waalkes Bedrijvenpark Twente no. 40 7602 KB , NETHERLANDS

Product	Price	Qty	Total
Ignition Platform and Core Drivers - Ignition Platform - OPC UA Server Module - Core Drivers	\$1,000.00	1	\$1,000.00 \$0.00
Vision Limited / 3 Clients Limited edition of the Vision Module.	\$2,660.00	1	\$2,660.00 \$1,862.00
Tag Historian Tag Historian. Unlimited data points.	\$2,000.00	1	\$2,000.00 \$1,400.00
Reporting Module Embedded / 3 Clients Creates dynamic, database-driver PDF reports.	\$1,000.00	1	\$1,000.00 \$700.00
OPC-COM Module Bridge that exposes COM based OPC-DA servers to the system.	\$400.00	1	\$400.00 \$280.00
Wire Transfer Wire transfer charge	\$42.00	1	\$42.00
Price			\$7,102.00
HMI/SCADA Platform Discount			- \$1,000.00
HMI/SCADA OEM Discount			- \$1,818.00
Subtotal			\$4,284.00
Sales Tax @ 0%			\$0.00

Balance due by Oct 28, 2021

\$4,284.00

ALL CUSTOMER TERMS AND CONDITIONS ("TS & CS") RELATING TO THIS ORDER, WHEREVER LOCATED, ARE SUBJECT TO THE IGNITION BY INDUCTIVE AUTOMATION® SOFTWARE LICENSE AGREEMENT ("IASLA"). IF THERE IS A CONFLICT BETWEEN CUSTOMERS TS & CS AND THE IASLA, THE TERMS OF THE IASLA SHALL CONTROL. BY USE OF THE IGNITION SOFTWARE, YOU AGREE TO THIS REVISION TO YOUR TS & CS.





Invoice #1213709

Created: September 28, 2021 Payment Terms: Net 30

P.O. # 1249797

If paid after Oct 28, 2021

* \$4,712.40

* Buyer shall pay invoices within Net 30 days of the date of Buyer's receipt of each invoice. Failure to timely make the required payment shall result in a late fee of ten percent (10%) of the outstanding amount due as well as interest accruing on the outstanding balance from its due date until paid in full at a rate of ten percent (10%) per annum. All payments shall be first applied to any late fees and accrued interest.

Comments

The software is delivered electronically. Vendor No. 03635

Thank you for your order!

Your Account Manager, Vannessa Garcia 916-456-1045 x231 vannessa@inductiveautomation.com

THANK YOU!

Notes

This invoice was generated on September 28, 2021 and payment is due on October 28, 2021.

Please remit to: PO Box 2030, Folsom, CA 95763 USA

This contractor and subcontractor shall abide by the requirements of 41 CFR §§ 60⁻1.4(a), 60⁻300.5(a) and 60⁻741.5(a). These regulations prohibit discrimination against qualified individuals based on their status as protected veterans or individuals with disabilities, and prohibit discrimination against all individuals based on their race, color, religion, sex, or national origin. Moreover, these regulations require that covered prime contractors and subcontractors take affirmative action to employ and advance in employment individuals without regard to race, color, religion, sex, national origin, protected veteran status or disability.

ALL CUSTOMER TERMS AND CONDITIONS ("TS & CS") RELATING TO THIS ORDER, WHEREVER LOCATED, ARE SUBJECT TO THE IGNITION BY INDUCTIVE AUTOMATION® SOFTWARE LICENSE AGREEMENT ("IASLA"). IF THERE IS A CONFLICT BETWEEN CUSTOMERS TS & CS AND THE IASLA, THE TERMS OF THE IASLA SHALL CONTROL. BY USE OF THE IGNITION SOFTWARE, YOU AGREE TO THIS REVISION TO YOUR TS & CS.

Software License Certificate





License Key: JNP-KTH

License Location: 7602 KB Issue Date: September 28, 2021 Updated: September 28, 2021

The license for Ignition can be activated on the version listed or prior versions of Ignition.

Platform	Version	Description
Ignition Platform	8.1	Standard
Modules		Description
Visualization		
Reporting Module		Embedded
Symbol Factory		Standard
Vision Module		Limited, 3 Clients
Drivers and Connectivity		
UDP/TCP Driver Module		Standard
Omron Driver		Standard
BACnet Driver Module		Standard
OPC-COM Module		Standard OPC-COM
Siemens Driver Module		Standard
Modbus Driver Module		Standard
Allen-Bradley Drivers Mode	ule	Standard
OPC-UA Server Module		Standard
DNP3		Standard
ControlLogix v21+ Driver		Standard
Data and Logic		
Tag Historian		Standard

Software License Certificate





License Key: JNP-KTH

License Location: 7602 KB Issue Date: September 28, 2021 Updated: September 28, 2021

The license for Ignition can be activated on the version listed or prior versions of Ignition.

Support	Description
No Support Plan	To add Support to your license contact sales@inductiveautomation.com



Activation Instructions

Your software activation is delivered electronically as a six-digit code, or license key. There is only one activation per key. Use this license key to activate the software through the Ignition Gateway.

- If you have purchased a new license follow the New License Activation procedure
- If you have purchased additional modules for an existing license, follow the Updating an Existing License procedure
- To move the license from one server to another follow the Unactivating an Existing License procedure followed by the New License Activation procedure

For complete instructions please refer to the Licensing and Activation section of our User Manual: https://docs.inductiveautomation.com/

New License Activation

Online Activation - Ignition Gateway has internet connectivity

- 1. Navigate to the Config Section on the Gateway Webpage http://localhost:8088.
- 2. From the menu on the left, select System > Licensing.
- 3. Click the Activate License button.
- 4. Enter your License Key and click Submit.
- 5. Click the Activate button.

The Licensing page will refresh, and your Current License will be successfully activated.

Offline Activation - Ignition Gateway has no internet connectivity

When you do not have an internet connection on the installation machine, you must activate your license manually.

- 1. Navigate to the Config Section on the Gateway Webpage http://localhost:8088.
- 2. From the menu on the left, select System > Licensing. Click the Offline Activation button.
- 3. Click the Download Activation Request. An activation request file, called activation_message.txt is generated.
- 4. Take the activation_message.txt file to a machine with Internet access and go to Support Home Page.
- 5. Click Choose File and select the activation message.txt file.
- 6. Once you upload the activation_message.txt file, a license file called license.ipl is generated.
- 7. Bring the license ipl file back to the computer on which you're licensing Ignition.
- 8. Back on the Offline Activation page, upload the license ipl file. Then click Activate to finish the process.

The Licensing page will refresh showing your license was successfully activated.



Activation Instructions Continued

Updating an Existing License

If you added one or more new modules to an existing license, then you'll need to update (Reactivate) the license.

- 1. If the gateway has internet access, you update a license from the Config > Licensing section on the Gateway webpage.
- 2. Simply click the Reactivate button next to the license that was changed. Pressing the Reactivate button will cause the gateway to attempt to reach out to our licensing server, and will update shortly after.

If the gateway does not have internet access, contact your Sales Representative to have your license reset.

Unactivating an Existing License

If you want to activate Ignition on a different server, you must first unactivate it on the current server.

- 1. To unactivate the Gateway navigate to the Config section of Gateway Webpage.
- 2. From the menu on the left, select System > Licensing. Click on the Unactivate License icon.
- 3. A Licensing / Confirm Unactivate window will appear asking you to confirm the unactivation. Click the Yes, Unactivate button.

It may take a minute or so for the request to finish. The unactivation request will be sent to Inductive Automation's licensing servers, and the license will again be available for activation on another Gateway.

Emergency Activation

In cases where you may have a hardware or OS failure and you cannot unactivate a license, Ignition provides an Emergency Activation mode. In this mode, you can temporarily activate your license for 7 days giving you enough time to contact Inductive Automation Support. Activating your license in emergency mode is exactly the same as activating with your normal license, you don't have to do anything different because Ignition handles it all for you.



Remittance Information

Please see the following options on how to remit your payment

Electronic Payments

Credit Card:

Email accounting@inductiveautomation.com with the invoice number and email address of the payer. A link will be sent to the payer's email in order to pay online.

Automated Clearing House (ACH):

ZB, N.A. dba California Bank & Trust ABA routing number: 121002042 Account number: 5790368079

Wire Transfers:

ZB, N.A. dba California Bank & Trust ABA routing number (domestic): 121002042 Swift code (foreign): ZFNBUS55 Account number: 5790368079

Include your order number in the payment details field, and email remittance information to accounting@inductiveautomation.com

Check Payments

Remit check to:

Inductive Automation LLC PO Box 2030 Folsom, CA 95763