

Introduction to content parts

from 1.2.9 and above

Head area

All content types have the following setting possibilities:

In the head area you will find the following setting possibilities.



Head area of content type / content part

» Field descriptions

category Press to go to the site structure of this article. Also look for Create / **Edit Site Structure** Article title Press nto go to the site article title of this article.

Also look for Create

<u>Article</u>

Important: When you use one of the links at **category** or **article title** before you have saved die used content part, the changes get lost.

Content type

Here you choose the content type / content part that you want to

use.

Important: NEVER change the content type / content part when you already have inserted content. It doesn't matter whether it was saved or not, because the content will be deleted. When you want to change the content type, copy the whole content, then xhange the content type and paste the content again.

Output

here you can say in which area the content part will be shown.

You have the following possibilities:

Main Block(CONTENT)

Left(LEFT)
Right (RIGHT)
Header (HEADER)
Footer (FOOTER)
Here you can define a

Space before / after

space between the actual and the following content block / content

part.

Top-Link Here you can show a

link to the begin of the

article.

Result: ATOP

The graphic can also be changed. You can find it

/img/article/top_link_0.gif

Anchor

Here you can set an anchor, that means you can directly link to a content part.

When you have set a check here, the following code fragment will be generated: XXX is the ID of the content part.

How can you see the ID of the content part? You can find it here:

The article center in detail

To call an anchor in an article, please use one of the following possibilities:

1. Anchor inside of an article

Insert the following link:

<u>Linktext</u> XXX will be replaced with the ID of the content part.

2. Anchor in an other articleInsert the following link:Linktext

In this case "Alias" will be replaced with the structure name in that the article is located and xxx will be replaced again with the ID of the content part.

the second example has been used at "The article center in detail".

Notice: Please note that **#cpid** is always written

small.

Sort. Value

Content title Content title of the

actual CP

Sub title Sub title of the actual

CP

∧TOP

Footer

View to a newly created content type / content part

In the footer you can find the following settings and change possibilities or buttons.



Footer of the content type / content part

Footer

» Feldbeschreibungen

Status Here you can decide with a check whether the CP is visible for the visitor or not.

checked = CP visible

unchecked = CP not visible (Standard)

Create The CP will be created, but you can continue to work with it.

Save The CP will be created, but the View will be closed and you will jump to a summary of all CPs

in this article.

Cancel The CP will be closed without savings.

Notice: All already inserted data will be deleted.

∧TOP

Footer

View to a already created content type / content part

The view differs at a new created content type / content part as follows.

In the footer you can find the following settings and change possibilities or buttons.



Fusszeile des Inhaltstyps / Contentparts

» Field descriptions

Status here you decide whether the CP is visble for the visitor or not

checked = CP visible

unchecked = CP invisible (Standard)

Actualize The changes will be saved and you can continue to work in this view.

Save The changes will be saved and the view will be closed. You are going back to the CP

overview.

Cancel The CP will be closed without savings.

Notice: Alle inserted changes will be deleted.

Preview Pressing this button shows the actual area as shown to the visitor.

∧TOP

URL: http://www.phpwcms-docu.de/index.php?content_parts_en