

# Module-2 (Assignment Day-4)

1. Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.



- 1) **Connect the webcam:** Plug the USB webcam into an available USB port on the computer.
- 2) **Wait for detection:** Windows should automatically detect the webcam and install the required driver.
- 3) **Check the driver:** If Windows does not install it automatically, open **Settings** → **Windows Update** and check for updates.
- 4) **Open Camera:** Click **Start** and search for **Camera**, then open the Camera app.
- 5) **Check the video:** If the webcam is working, you should see your live video on the screen.
- 6) **Capture a photo:** Click the **camera button** in the Camera app to take a photo.
- 7) **Verify the photo:** Open the saved photo to confirm that the webcam captured the image clearly.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.



### **Setting Up a Local Printer:**

- 1) **Connect the printer:** Connect the printer to the computer using a USB cable or connect it to the same Wi-Fi network as the computer.
- 2) **Turn on the printer:** Make sure the printer has paper and enough ink or toner.
- 3) **Install the driver:** Windows may install the driver automatically. If not, download and install the correct driver for the printer model.
- 4) **Add the printer:** Go to Settings → Bluetooth & devices → Printers & scanners → Add device.
- 5) **Select the printer:** Choose your printer from the list and complete the setup.
- 6) **Set as default:** If needed, select the printer and choose Set as default.
- 7) **Print a test page:** Open the printer settings, select Print test page, and wait for the page to print.
- 8) **Check the result:** Make sure the test page prints correctly without missing text or lines.

3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.



#### **Resolve “Printer not Detected” Problem:**

- 1) **Unplug the printer:** Turn off the printer and remove the USB cable from the computer.
- 2) **Check the problem:** Open **Device Manager** by right-clicking the Start button and selecting Device Manager.
- 3) **Look for an error:** Check Printers, Print queues, or Universal Serial Bus controllers for the printer. Look for a yellow warning icon.
- 4) **Reconnect the printer:** Plug the USB cable back into the computer and turn on the printer.
- 5) **Scan for changes:** In Device Manager, click Action → Scan for hardware changes.
- 6) **Check the printer again:** Windows should detect the printer and show it in Device Manager.
- 7) **Update the driver if needed:** If there is still a warning icon, right-click the device and select Update driver.
- 8) **Test the printer:** Open Printers & scanners in Windows Settings and print a test page.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.



#### **Steps to Fix Webcam Not Working in Zoom:**

- 1) **Check the Camera app:** Open the Windows Camera app and make sure the webcam works there.
- 2) **Close other apps:** Close the Camera app and any other apps that may be using the webcam, such as Teams or Skype.
- 3) **Check Zoom permission:** Go to Settings → Privacy & security → Camera and make sure Camera access and Let desktop apps access your camera are turned on.
- 4) **Check Zoom settings:** Open Zoom and go to Settings → Video.
- 5) **Select the webcam:** Under the camera option, select the correct webcam from the list.
- 6) **Test the video:** Check the preview to see if your video is displayed.
- 7) **Restart Zoom:** If the webcam still does not work, completely close Zoom and open it again.
- 8) **Restart the computer:** If needed, restart the computer and test the webcam again.