

Lab Report

Lab Report

Time Spent: 00:05

Score: 0/5 (0%)

Not Passed

Passing Score: 5/5 (100%)

TASK SUMMARY

Required Actions

Configure Snort rulesShow Details

Configure Sourcefire OpenAppID DetectorsShow Details

Configure the Rules Update SettingsShow Details

Configure General SettingsShow Details

Configure the Snort Interface settings for the WAN interfaceShow Details

EXPLANATION

Complete this lab as follows:

1. Sign into the pfSense management console.
 - a. In the Username field, enter **admin**.
 - b. In the Password field, enter **P@ssw0rd** (zero).
 - c. Select **SIGN IN** or press **Enter**.
2. Access the Snort Global Settings.
 - a. From the pfSense menu bar, select **Services > Snort**.
 - b. Under the *Services* breadcrumb, select **Global Settings**.
3. Configure the required rules to be downloaded.
 - a. Select **Enable Snort VRT**.
 - b. In the Sort Oinkmaster Code field, enter **992acca37a4dbd7**. You can copy and paste this from the scenario.
 - c. Select **Enable Snort GPLv2**.
 - d. Select **Enable ET Open**.
4. Configure the Sourcefire OpenAppID Detectors to be downloaded.
 - a. Under Sourcefire OpenAppID Detectors, select **Enable OpenAppID**.
 - b. Select **Enable RULES OpenAppID**.
5. Configure when and how often the rules will be updated.
 - a. Under Rules Update Settings, use the **Update Interval** drop-down to select **4 DAYS**.
 - b. For Update Start Time, change to **00:10**.
 - c. Select **Hide Deprecated Rules Categories**.
6. Configure Snort General Settings.
 - a. Under General Settings, use the **Remove Blocked Hosts Interval** drop-down to select **1 Day**.
 - b. Select **Startup/Shutdown Logging**.
 - c. Select **Save**.
7. Configure the Snort Interface settings for the WAN interface.
 - a. Under the Services breadcrumb, select **Snort Interfaces** and then select **Add**.
 - b. Under General Settings, make sure **Enable interface** is selected.
 - c. For Interface, use the drop-down to select **WAN (CorpNet_pfSense_L port 1)**.
 - d. For Description, use **Snort-WAN**.
 - e. Under Alert Settings, select **Send Alerts to System Log**.
 - f. Select **Block Offenders**.
 - g. Scroll to the bottom and select **Save**.
8. Start Snort on the WAN interface.
 - a. Under the Snort Status column, select the **arrow**.
 - b. Wait for a checkmark to appear, indicating that Snort was started successfully.