

29 de Octubre de 2025

Diego Alejandro Quiroz Ruiz

2º ASIR

PRÁCTICA TERMINALES



Enunciado.

1.- Instalar un servidor SSH en Linux

- Crear usuarios que puedan acceder al equipo a través del ssh (adduser)
- Instalar el servidor ssh (Ubuntu, Knoppix)
- Probar con Putty desde Windows
- Y probar desde otro Linux con el comando ssh

1.b.- ¿Cómo se podría conectar un usuario sin tener que meter la contraseña cada vez que se conecta?

2.- Conexión de escritorio remoto en Windows (RDP)

Levantar el servicio RDP en windows

Conexión cliente RDP desde:

- Windows
- Linux (Remmina)

3.- Instalar un Teamviewer en equipo windows y en otro Linux

- conectar a administración remota desde:
 - Otro equipo windows y desde otro Linux
 - Desde móvil
- conectar en modo presentación y ver las opciones disponibles
 - Otro equipo windows y desde otro Linux
 - Desde móvil

Trabajo.

1. Instalar un servidor SSH en Linux

- Crear usuarios que puedan acceder al equipo a través del ssh (adduser)

```
AFH Ubuntu Server [Corriendo] - Oracle VM VirtualBox
smr@ubuntuserver:~$ sudo adduser diegoalejandroquirozruiz
Adding user `diegoalejandroquirozruiz' ...
Adding new group `diegoalejandroquirozruiz' (1001) ...
Adding new user `diegoalejandroquirozruiz' (1001) with group `diegoalejandroquirozruiz' ...
Creating home directory `/home/diegoalejandroquirozruiz' ...
Copying files from `/etc/skel' ...
New password:
Retype new password:
passwd: password updated successfully
Changing the user information for diegoalejandroquirozruiz
Enter the new value, or press ENTER for the default
  Full Name []:
    Room Number []:
    Work Phone []:
    Home Phone []:
    Other []:
Is the information correct? [Y/n] y
smr@ubuntuserver:~$
```

- Instalar el servidor ssh (Ubuntu, Knoppix)

```
GNU nano 4.8
# This is the network config writt
network:
  ethernet:
    enp0s3:
      dhcp4: false
      addresses: [192.168.10.2/24]
      gateway4: 192.168.10.1
      nameservers:
        addresses: [8.8.8.8]
    enp0s8:
      dhcp4: yes
  version: 2
```

```
smr@ubuntuserver:~$ sudo ip link set enp0s8 up
smr@ubuntuserver:~$ sudo dhclient enp0s8
RTNETLINK answers: File exists
```

```
smr@ubuntuserver:~$ sudo systemctl enable ssh
Synchronizing state of ssh.service with SysV service script with /lib/systemd/systemd-sysv-install.
Executing: /lib/systemd/systemd-sysv-install enable ssh
smr@ubuntuserver:~$ sudo systemctl start ssh
smr@ubuntuserver:~$ sudo systemctl status ssh
• ssh.service - OpenBSD Secure Shell server
   Loaded: loaded (/lib/systemd/system/ssh.service; enabled; vendor preset: enabled)
   Active: active (running) since Wed 2025-10-29 16:25:07 UTC; 1min 45s ago
     Docs: man:sshd(8)
           man:sshd_config(5)
   Main PID: 3492 (sshd)
     Tasks: 1 (limit: 1067)
    Memory: 1.8M
   CGroup: /system.slice/ssh.service
           └─3492 sshd: /usr/sbin/sshd -D [listener] 0 of 10-100 startups

Oct 29 16:25:07 ubuntuserver systemd[1]: Starting OpenBSD Secure Shell server...
Oct 29 16:25:07 ubuntuserver sshd[3492]: Server listening on 0.0.0.0 port 22.
Oct 29 16:25:07 ubuntuserver sshd[3492]: Server listening on :: port 22.
Oct 29 16:25:07 ubuntuserver systemd[1]: Started OpenBSD Secure Shell server.
smr@ubuntuserver:~$
```

- Probar con Putty desde Windows

Propiedades: Protocolo de Internet versión 4 (TCP/IPv4) X

General

Puede hacer que la configuración IP se asigne automáticamente si la red es compatible con esta funcionalidad. De lo contrario, deberá consultar con el administrador de red cuál es la configuración IP apropiada.

☐ Obtener una dirección IP automáticamente

☒ Usar la siguiente dirección IP:

Dirección IP: 192 . 168 . 10 . 10

Máscara de subred: 255 . 255 . 255 . 0

Puerta de enlace predeterminada: 192 . 168 . 10 . 2

☐ Obtener la dirección del servidor DNS automáticamente

☒ Usar las siguientes direcciones de servidor DNS:

Servidor DNS preferido: . . .

Servidor DNS alternativo: . . .

☒ Validar configuración al salir Opciones avanzadas...

Aceptar Cancelar

PuTTY Configuration ? X

Category:

- Session
- Logging
- Terminal
 - Keyboard
 - Bell
 - Features
- Window
 - Appearance
 - Behaviour
 - Translation
 - Selection
 - Colours
- Connection
 - Data
 - Proxy
 - SSH
 - Serial
 - Telnet
 - Rlogin
 - SUPDUP

Basic options for your PuTTY session

Specify the destination you want to connect to

Host Name (or IP address) 192.168.10.2 Port 22

Connection type:
☒ SSH ☐ Serial ☐ Other: Telnet

Load, save or delete a stored session

Saved Sessions

Default Settings

Load Save Delete

Close window on exit:
☐ Always ☐ Never ☒ Only on clean exit

About Help Open Cancel

```
diegoalejandroquirozruiz@ubuntuserver: ~  
login as: diegoalejandroquirozruiz  
diegoalejandroquirozruiz@192.168.10.2's password:  
Welcome to Ubuntu 20.04.1 LTS (GNU/Linux 5.4.0-96-generic x86_64)  
  
* Documentation:  https://help.ubuntu.com  
* Management:    https://landscape.canonical.com  
* Support:        https://ubuntu.com/advantage  
  
System information as of Wed Oct 29 16:52:51 UTC 2025  
  
System load:  0.0                Processes:            118  
Usage of /:   52.2% of 8.79GB    Users logged in:     1  
Memory usage: 26%               IPv4 address for enp0s3: 192.168.10.2  
Swap usage:   0%                IPv4 address for enp0s8: 10.0.3.15  
  
326 updates can be installed immediately.  
212 of these updates are security updates.  
To see these additional updates run: apt list --upgradable  
  
Failed to connect to https://changelogs.ubuntu.com/meta-release-lts. Check your  
Internet connection or proxy settings  
  
The programs included with the Ubuntu system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by  
applicable law.  
  
diegoalejandroquirozruiz@ubuntuserver:~$
```

- Y probar desde otro Linux con el comando ssh

```
GNU nano 7.2 /etc/netplan/50-cloud-init.yaml  
# This file is generated from information provided by the d  
# to it will not persist across an instance reboot. To dis  
# network configuration capabilities, write a file  
# /etc/cloud/cloud.cfg.d/99-disable-network-config.cfg with  
# network: {config: disabled}  
network:  
  ethernets:  
    enp0s3:  
      dhcp4: false  
      addresses: [192.168.10.20/24]  
      routes:  
        - to: 0.0.0.0/0  
          via: 192.168.10.1  
      nameservers:  
        addresses: [8.8.8.8]  
    enp0s8:  
      dhcp4: true  
  version: 2
```

```
diegoalejandroruiz@ubuntu:~$ ssh diegoalejandroruiz@192.168.10.2
The authenticity of host '192.168.10.2 (192.168.10.2)' can't be established.
ED25519 key fingerprint is SHA256:+tWYaZ2wV/D1T7BobRxlvgNEhm7cyTcUoowXm/jEigo.
This key is not known by any other names.
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
Warning: Permanently added '192.168.10.2' (ED25519) to the list of known hosts.
diegoalejandroruiz@192.168.10.2's password:
Welcome to Ubuntu 20.04.1 LTS (GNU/Linux 5.4.0-96-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/advantage

System information as of Wed Oct 29 17:14:44 UTC 2025

System load:  0.0               Processes:    123
Usage of /:   52.2% of 8.79GB   Users logged in: 2
Memory usage: 26%              IPv4 address for enp0s3: 192.168.10.2
Swap usage:  0%                IPv4 address for enp0s8: 10.0.3.15

326 updates can be installed immediately.
212 of these updates are security updates.
To see these additional updates run: apt list --upgradable

Failed to connect to https://changelogs.ubuntu.com/meta-release-lts. Check your Internet connection or proxy settings

Last login: Wed Oct 29 16:52:51 2025 from 192.168.10.10
diegoalejandroruiz@ubuntu:~$
```

1.b.- ¿Cómo se podría conectar un usuario sin tener que meter la contraseña cada vez que se conecta?

```
usuario@usuario:~$ ssh-keygen
Generating public/private ed25519 key pair.
Enter file in which to save the key (/home/usuario/.ssh/id_ed25519):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/usuario/.ssh/id_ed25519
Your public key has been saved in /home/usuario/.ssh/id_ed25519.pub
The key fingerprint is:
SHA256:cEQU0TD6Xk++VW9Isf4F0PaMr8ZH0Q2Y/R84ts/cgWU usuario@usuario
The key's randomart image is:
+--[ED25519 256]--+
|      o+=o      |
|      . oo      |
|      . . . . .++|
|      . o      ooo*|
|      . S .    BE=|
|      . . +    B+O+|
|      .  o oo=oO|
|      .  o .+=*|
|      .  .o=o|
+-----[SHA256]-----+
usuario@usuario:~$
```

```
usuario@usuario:~$ ssh-copy-id diegoalejandroruiz@192.168.10.2
/usr/bin/ssh-copy-id: INFO: attempting to log in with the new key(s), to filter out any that are already installed
/usr/bin/ssh-copy-id: INFO: 1 key(s) remain to be installed -- if you are prompted now it is to install the new keys
diegoalejandroruiz@192.168.10.2's password:

Number of key(s) added: 1

Now try logging into the machine, with: "ssh 'diegoalejandroruiz@192.168.10.2'"
and check to make sure that only the key(s) you wanted were added.

usuario@usuario:~$
```

```
usuario@usuario:~$ ssh diegoalejandroruiz@192.168.10.2
Welcome to Ubuntu 20.04.1 LTS (GNU/Linux 5.4.0-96-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/advantage
Papeleras
System information as of Wed Oct 29 17:57:52 UTC 2025

System load: 0.0          Processes:              122
Usage of /:  52.2% of 8.79GB Users logged in:                2
Memory usage: 26%         IPv4 address for enp0s3: 192.168.10.2
Swap usage:  0%           IPv4 address for enp0s8: 10.0.3.15

326 updates can be installed immediately.
212 of these updates are security updates.
To see these additional updates run: apt list --upgradable

Failed to connect to https://changelogs.ubuntu.com/meta-release-lts. Check your Internet connection or proxy settings


Last login: Wed Oct 29 17:14:45 2025 from 192.168.10.20
diegoalejandroruiz@ubuntuserver:~$
```

2. Conexión de escritorio remoto en Windows (RDP)

Levantar el servicio RDP en windows

Conexión cliente RDP desde:

- Windows



Propiedades: Protocolo de Internet versión 4 (TCP/IPv4)



General

Puede hacer que la configuración IP se asigne automáticamente si la red es compatible con esta funcionalidad. De lo contrario, deberá consultar con el administrador de red cuál es la configuración IP apropiada.

☐ Obtener una dirección IP automáticamente

☒ Usar la siguiente dirección IP:

Dirección IP:

Máscara de subred:

Puerta de enlace predeterminada:

☐ Obtener la dirección del servidor DNS automáticamente

☒ Usar las siguientes direcciones de servidor DNS:

Servidor DNS preferido:

Servidor DNS alternativo:

☒ Validar configuración al salir

Conexión a Escritorio remoto

**Escritorio remoto
Conexión**

General Pantalla Recursos locales Rendimiento Opciones de conexión

Configuración del inicio de sesión

Escriba el nombre del equipo remoto.

Equipo:

Usuario:

Se solicitarán credenciales al conectarse.

☒ Permitir guardar las credenciales

Configuración de la conexión


Guarde la configuración de conexión actual o abra una conexión guardada.

Seguridad de Windows

**Escribir las credenciales**

Estas credenciales se usarán para conectarse a 192.168.10.10.

**diegoquiroz****Usar otra cuenta**☒ Recordar mis credenciales



- Linux (Remmina)

