Type of Methods

- Instance Methods
 - Accessor Methods
 - Mutator Methods
- Class Methods
- Static Methods

Instance Method

Instance methods are the methods which act upon the instance variables of the class.

Instance method need to know the memory address of the instance which is provided through *self* variable by default as first parameter for the instance method.

```
Syntax:-

def method_name(self):
    function body

Instance Method without Parameter/Formal Arguments

def method_name(self, f1, f2):
    function body

Instance Method with Parameter/Formal Arguments
```

Instance Method without Parameter

```
class Mobile:
                                          class Mobile:
                        Instance Method
                                                                           Instance variable
                                             def init (self):
  def show model(self):
                                                  self.model = 'RealMe X
       print("RealMe X")
                                            def show model(self):
                                                                           Instance Method
                                                 print(self.model)
realme = Mobile()
                                                                     Accessing Instance variable
                                          realme = Mobile()
                                                                     Inside Instance Method
```

Calling Instance Method w/o Argument

Instance methods are bound to object of the class so we call instance method with object name.

```
Syntax:- object name.method name()
Ex:- realme.show model()
class Mobile:
  def show model(self):
       print("RealMe X")
realme = Mobile()
realme.show model()
                            Calling Instance Method w/o Argument
```

Instance Method with Parameter

```
class Mobile:
                                              Instance variable
              def init (self):
                   self.model = 'RealMe X'
                                             Instance Method with parameter
             def show model(self, p):
                → self.price = p
Instance Variable
                  print(self.model, self.price)
           realme = Mobile()
```

Calling Instance Method with Argument

```
Syntax:- object name.method name(Actual argument)
Ex:- realme.show model(1000)
class Mobile:
  def init (self):
       self.model = 'RealMe X'
  def show model(self, p):
       self.price = p
       print(self.model, self.price)
realme = Mobile()
realme.show_model(1000)
                                Calling Method with argument
```

Accessor Method

This method is used to access or read data of the variables. This method do not modify the data in the variable. This is also called as getter method.

```
Ex:-
                                        class Mobile:
def get value(self):
                                           def init (self):
def get result(self):
                                               self.model = 'RealMe X'
def get name(self):
                                           def get model(self):
def get id(self):
                                                return self.model
                                        realme = Mobile()
                                        m = realme.get model()
                                        print(m)
```

Mutator Method

This method is used to access or read and modify data of the variables. This method modify the data in the variable. This is also called as setter method.


```
Ex:-
                     class Mobile:
                                                         class Mobile:
def set value(self):
                       def init (self):
def set result(self):
                            self.model = 'RealMe
                                                           def set model(self, m):
def set name(self):
                                                                self.model = m
def set id(self):
                       def set model(self):
                                                         realme = Mobile()
                            self.model = 'RealMe
                                                         realme.set model('RealMe X')
                     2'
                     realme = Mobile()
                     realme.set model()
```

Class Methods

Class methods are the methods which act upon the class variables or static variable of the class.

Decorator @classmethod need to write above the class method.

By default, the first parameter of class method is cls which refers to the class itself.



Class Method without Parameter

```
class Mobile:
                                                class Mobile:
                                                                     Class Variable
                           Decorator
                                                   fp = 'Yes'
  @classmethod
                                                                           Decorator
                                Class Method
  def show model(cls):
                                                  @classmethod
                                                  def show model(cls):
       print("RealMe X")
                                                                                Class Method
                                                       print(cls.fp)
realme = Mobile()
                                                                      Accessing Class variable
                                                realme = Mobile
                                                                      Inside Class Method
```

Calling Class Method without Argument

```
Syntax:- Classname.method name()
class Mobile:
  @classmethod
  def show model(cls):
       print("RealMe X")
realme = Mobile()
Mobile.show model()
                            Calling Class Method w/o Argument
```

Class Method with Parameter

```
class Mobile:
Class Variable
                • fp = 'Yes'
                                                  Defining Method with parameter
                • @classmethod
   Decorator
                 def show model(cls, r):
                      cls.ram = r
                      print(cls.fp, cls.ram)
              realme = Mobile()
```

Calling Class Method with Argument

```
Syntax:- Classname.method name(Actual argument)
Ex:- Mobile.show model('4GB')
class Mobile:
   fp = 'Yes'
   @classmethod
  def show model(cls, r):
       cls.ram = r
       print(cls.fp, cls.ram)
realme = Mobile()
Mobile.show model(101)
```


Calling Method with argument

Static Methods

Static Methods are used when some processing is related to the class but does not need the class or its instances to perform any work.

We use static method when we want to pass some values from outside and perform some action in the method.

Decorator @staticmethod need to write above the static method.



Static Method without Parameter

```
class Mobile:

@staticmethod

def show_model():

print("RealMe X")

realme = Mobile()

class Mobile:

fp = 'Yes'

@staticmethod

def show_model():

print(Mobile.fp)

realme = Mobile()
```

Calling Static Method without Argument

```
Syntax:- Classname.method name()
class Mobile:
  @staticmethod
  def show model():
       print("RealMe X")
realme = Mobile()
Mobile.show model()
                           Calling Static Method w/o Argument
```

Static Method with Parameter

class Mobile:

```
Decorator

@staticmethod
def show_model(m, p):

model = m
price = p
print(model, price)
realme = Mobile()
```

Calling Static Method with Argument

```
Syntax:- Classname.method name(Actual argument)
Ex:- Mobile.show model(1000)
class Mobile:
   @staticmethod
  def show model(m, p):
       model = m
       price = p
       print(model, price)
realme = Mobile()
Mobile.show model('RealMe X', 1000)
                                            Calling Method with argument
```