

DYNAMICS GUARD

Envelope, transient, pressure, and containment control


Control entry, impact, sustain, and pressure without hiding the source.

Included products: ANUBIS, OTIS, DEBO, LOOKOUT

Recommended route: Use on individual tracks or buses according to Smart Position. DEBO may be used for parallel impact.

Family preset law: Factory presets describe musical intent and expose the useful range of the plugin. They do not change protected Input, Mix, Output, Power, or final ceiling controls unless the plugin's explicit canon requires it. Cathedral and SacredVerb retain their protected preset behavior. Preset changes must remain clickless.

ANUBIS



Dynamics gate and guard with threshold, ratio, attack, hold, release, range, a named stereo host Sidechain bus, independent Sidechain Key and Sidechain Duck operation, protected I/O, and parallel mix.

Preferred placement: Insert Safe. Use directly on a source or instrument channel and bypass-match before committing.

Core controls

- Input
- Mix
- Output
- Power
- Threshold
- Ratio
- Attack
- Hold
- Release

Sidechain Key: route a kick, vocal, guide track, or other key signal to the named stereo Sidechain bus, then enable Sidechain Key. The key drives detection only and is not mixed into the output.

Sidechain Duck: enable Duck when the routed sidechain should push the main program down. Key and Duck are independent controls; with neither enabled, ANUBIS detects from the main input.

Wave colors: yellow/gold means coherent center energy and mono-safe passage; purple means stereo width or phase spread; red means anti-phase or threshold-danger behavior that should be corrected or eased.

Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
IN	Main-input RMS energy	Shows the program feeding the gate.
GATE	Current gate passage gain	OPEN is full passage; lower values mean attenuation.
KEY	External sidechain RMS energy	Moves only when a host sidechain is routed.
DUCK	Sidechain-driven gain reduction	More fill means deeper ducking of the main signal.
OUT	Post-gate RMS energy	Compare with IN to judge actual attenuation.


Display	What it measures	How to read it
Transfer graph	Threshold, envelope, and Range floor	Shows where the signal opens and how far closure may fall.
Correlation waves	Left/right phase relationship	Gold is coherent, purple is spread, red warns of anti-phase risk.

Additional controls are mapped in the family technical manual.

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

OTIS



3-6-9 macro dynamics processor: Micro Peak controls short events, Meso Density shapes body, and Macro Level governs the long envelope.

Preferred placement: Insert Safe. Use directly on a source or instrument channel and bypass-match before committing.

Core controls

- Micro Peak
- Meso Density
- Macro Level
- Makeup Gain
- Gain Match

Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
INPUT	Input peak in dB	Confirms level feeding all three time scales.
RESPONSE	Strongest active 3/6/9 reduction	Shows the greatest current reduction across Micro, Meso, or Macro.
OUTPUT	Output peak in dB	Use with INPUT and Gain Match for fair comparison.
3 / Micro activity	Fast transient reduction	Responds to short peaks and front edges.
6 / Meso activity	Body and phrase-density reduction	Responds to medium-duration energy.
9 / Macro activity	Long-envelope reduction	Responds to sustained level movement.


Current factory programs detected

OTIS PRESET

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

DEBO



Pressure-activated dynamics processor with nine updated canonical programs using the restored iCloud names. The approved powered-on default is unchanged; the named bank uses a warmer depth/pressure progression without runtime preset clamping, topping out at 2.2 dB Maximize.

Preferred placement: Insert Safe. Use directly on a source or instrument channel and bypass-match before committing.

Core controls

- Power
- Flower of Life
- Gain Match
- Input
- Drive
- Maximize
- Depth
- Clarity
- Output

Use VOCAL HOLD as the tonal reference for the bank. The nine updated canonical programs restore the iCloud names and progress from restrained control to stronger pressure without flattening their musical differences.

The presets are intentionally not runtime-clamped. RED LINE WATCH is the strongest factory stage at 4.2 dB Maximize.

Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
RMS	Sustained signal body	Shows average energy driving the pressure model.
GUARD PRESSURE	Combined density/containment demand	Higher values mean DEBO is working harder.
PEAK	Fast peak relative to ceiling	Approaching the top warns of limited remaining space.
GOVERNOR	Gain held back by protection	More activity means stronger safety containment.
Pressure window / face	RMS-driven pressure stage	The visual advances with real pressure; red is the ceiling warning state.


Current factory programs detected

NO BRICKS [Stereo]; VOCAL HOLD [Stereo]; BRICK TAP [Stereo]; WALL PRESSURE [Stereo]; SHOULDER CHECK [Stereo]; NO SCISSORS [Stereo]; BREAKTHROUGH [Stereo]; RED LINE WATCH [Stereo]; PHI GUARD [Stereo]

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

LOOKOUT



Dual-envelope transient/sustain shaper. Attack and Sustain directly move the level of the transient and sustain portions of the signal, up to +/-18 dB each, ahead of the DIH tone-color stage. Its Eye of Heru state also gives live advisory guidance on transient/sustain balance while it shapes.

Preferred placement: Insert Safe. Use directly on a source or instrument channel and bypass-match before committing.

Core controls

- Power
- Attack
- Sustain
- Gain Match

Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
Transient	Detected front-edge energy	Use to judge whether Attack is emphasizing or restraining hits.
Sustain	Detected body and tail energy	Use to judge Sustain changes to ring, room, and body.
Alert	Potential transient/sustain imbalance	Higher values suggest the balance needs attention.
Miss	Underrepresented event energy	Indicates material that may be disappearing.
Stress	Over-concentrated envelope pressure	Reduce shaping intensity when stress remains high.
Composure	Stable transient/sustain balance	Higher is calmer and more controlled.
Eye of Heru	Combined advisory state	It reports balance; it does not move controls automatically.

Current factory programs detected

NEUTRAL SENTINEL [Stereo]; VOCAL FRONT GUARD; DRUM SNAP LOCK; KICK BODY ANCHOR; PERCUSSION EDGE; ROOM TAIL WATCH; MIX BUS COMPOSURE; FINAL PEAK SENTINEL

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.