

UTILITY OBSERVATION Technical Manual

Observation, metering, and print confirmation

Observe final behavior without becoming a tone-changing stage.

Included products: SESHAT

Routing authority: Place Seshat at the end of the analysis and print lane.

Canon baseline

Normalized control 1 equals 0.809016994 (PHI/2). Standard knob travel is 7 o'clock to 5 o'clock. Factory programs must be clickless and must honor protected I/O, Mix, Power, and ceiling controls. Smart Position remains the placement authority.

SESHAT

Final observation and analysis lane with restored spacious panel layout and optional peak hold; Full Observation shows the complete meter set, while each named preset shows only the meter or panel relevant to that view. It is not a tone-shaping processor.

Declared product: SESHAT | **Version:** 3.22 | **Customer formats:** macOS: Audio Unit (AU) and VST3; Windows beta: VST3 x64

Placement: Observation | **Channel mode:** detected | **Dual-mono link:** detected

Source-review status

- Exact DIHEngine::processSample call detected
- outputCeiling call detected
- No restricted DSP marker detected by the current source scan

Parameter surface

ID	Display name	Type
hold_peaks	Hold Peaks	Bool
gainmatch	Gain Match	Bool
channelmode	Channel Mode	Choice
dualmonolink	Dual Mono Link	Choice

Artwork authority

source/Seshat.png

Meter and visualizer semantics

Display	What it measures	How to read it
LUFS / BODY READ	Short-window perceptual loudness	Use for loudness context, not as the only delivery decision.
LEFT INPUT / RIGHT OUTPUT	Peak, RMS body, impact, and held peak	Shows entry and exit behavior; Hold Peaks retains the highest marker.
CORRELATION / MONO SAFETY	Left/right phase relationship	+1 is coherent, 0 is wide/uncorrelated, negative values risk cancellation.
SOLFEGGIO FREQUENCIES	Energy near the seven displayed resonant bands	Shows tonal concentration around 396 through 963 Hz.
IMPACT	Fast peak relative to the canon ceiling	Higher means stronger transient force.
FIELD	Body RMS plus stereo-side pressure	Higher means denser sustained spatial load.
MOMENTUM	Change in impact plus transient shape	Higher means faster, more active movement.
PHI ALIGNMENT	Proximity to DIH golden-ratio checkpoints	Higher means field pressure sits nearer a PHI reference point.
INTEGRITY	Similarity between impact and field pressure	Higher means transients and body remain proportionate.
CROWN	Weighted combined observation score	Summarizes impact, field, momentum, alignment, and integrity.
MOON	Transient shape plus momentum	Higher means stronger forward or launching behavior.
HF RISK	High-frequency energy imbalance	Higher values warn of potential harshness.
PHASE RISK	Correlation and side-energy danger	Higher values warn of mono cancellation.
LEVEL RISK	Peak/ceiling and transient danger	Higher values warn of insufficient headroom.

Display	What it measures	How to read it
COMFORT	Alignment, integrity, and low-risk balance	Higher values indicate a more stable field.
ADVISOR	Combined risk recommendation	A diagnostic suggestion; it does not change audio.
REEL 1 - Impact	Transient-force rank	First reel; 396 is low and MOON is highest.
REEL 2 - Field	Sustained spatial-pressure rank	Second reel; numbers are symbolic stages, not Hz.
REEL 3 - Momentum	Motion/transient-change rank	Third reel; higher stages mean more movement.
REEL 4 - Alignment	PHI-alignment rank	Fourth reel; higher stages mean closer alignment.
REEL 5 - Moon	Forward-propulsion rank	Fifth reel; higher stages mean stronger launch.

Preset view state controls panel visibility, not merely highlight color: Full Observation enables the full panel set; named views enable only their mapped meter/panel.