

Start here

What this set covers, who it is for, and what it deliberately leaves out.

You already know MultiValue. This set does not teach it.

SD Core for Windows is a version of SD, with elements found in the main SD version and in ScarletDME. ScarletDME was a fork of the original GPL release of OpenQM 2.6.6.

That lineage matters when you go looking for documentation. Not all the features of the **commercial** OpenQM 2.6.6 were in the GPL release, and **no documentation specific to the GPL version was ever released**. So even the OpenQM documents are not authoritative here.

The OpenQM 2.6.6 documents can be used as a reference, but SD Core has additions, changes and deletions — of features, of structure, of security and of commands. **These pages cover those changes.**

If you have used OpenQM, or SD on Linux, much of SD Core will still be familiar: the same data model, the same query processor, the same BASIC.

What "used to" means in these pages

These pages describe changes, so **used to**, **no longer** and **now** run all through them. **The comparison is against the code this version was made from** — SD on Linux, and ScarletDME and OpenQM 2.6.6 behind it.

It never means an earlier release of SD Core for Windows, because this is the first one. Some of the changes are Windows-only and have no Linux original to differ from; those say **earlier builds of this port** instead, so the two are never confused.

The pages

There are nineteen, and they are numbered. Read them in numerical order the first time; after that they stand alone.

A number with a letter after it is the second half of a long page, split so that no page runs longer than a reader will scroll: 01a continues 01, and so on. Nothing was renumbered when they were split.

00	Start here	this page — what the set is and what it leaves out
00a	Copyright and licence	The copyright and the licence for this set, in full and in one place

01	Installing SD Core	What the installer does, the two kinds of installation, and the choices it offers
01a	Upgrading and uninstalling	Installing a new release over an existing one, and taking SD off the machine
02	Your first thirty minutes	Start here if you just want it working — install to a second user signing in, in eight steps
03	Running SD	The service, starting and stopping, and recovering from an unclean shutdown
04	Scheduled jobs	Running an SD command on a timer, and the permit list that decides which ones
05	Account types	Standard, Programmer, Administrator, Suspended and Group — what each one is, and how to make one
05a	Managing accounts	Group accounts, sharing one, changing an account afterwards, and deleting it
06	Administrator commands	The verbs an administrator account gets, and how to use them
07	Programmer commands	The development verbs a standard account does not get
08	ssh access	How people reach SD on this machine, and why it is ssh
09	API access	The client API, its port, and the login that replaced the old one
10	Client distribution	Which library an application needs, and the one file no installer can update
11	Lower case	Case in commands, file names, record ids and account names
12	Security	The identity model, and what protects the database
12a	Security and the operating system	Reaching the machine from inside SD, how privileged work is done, and the audit trail
13	Other hardening	Auditing, the shell permit list, and the rest
14	Not in SD Core	What has been removed, and what to use instead

The five things most likely to surprise you

1. Signing in asks for no password. Windows has already authenticated you. `sd` puts you in the SD account with your own name; if there is no such account, or you are not in the `sdusers` group, you are refused. Administration is gated on being an elevated Windows administrator, not on a secret SD holds. See Security.

2. Accounts SD creates cannot log in to Windows at this machine. They are denied the physical console and Remote Desktop, deliberately. They reach SD **over ssh, or through an API client, or both** — and which of those is a required keyword on `create.account`. **Multi-user access over Remote Desktop is not supported** and is not a gap to be filled later. See ssh access and API access.

3. A new account gets a reduced VOC unless you say otherwise. A standard account cannot compile, catalogue, edit or create files. `programmer` and `administrator` keywords on `create.account` decide that. See Account types.

4. Commands and names are lower case now. Everything that can be lower case is. Typing in upper case still works — the lookup tries what you typed, then lower, then upper. See Lower case.

5. The API login is SCRAM, and the old cleartext one is gone. Clients built against the old protocol will not connect. See API access.

What this release is

W1.0-0. Windows only. There are no `#ifdef` branches keeping Linux alive in this source — Linux SD is a separate project and this is not a build of it.

It is a hobby project with no release schedule.

This set is the delta. It covers installing SD Core on Windows, running it, and what differs from OpenQM and from SD on Linux. The reference for the language and the command processor is a separate set, and so is the administrator's.

Where the source is

Both repositories are public, and everything in them is open source. SD is GPL software — `config_gpl` at an `sd` prompt displays the licence, and the installed tree carries it as a file.

The server, the client libraries and the installer	https://github.com/dmontaine/sd4windows
--	---

These pages	https://github.com/dmontaine/SDCoreWindowsDocs
-------------	---

Neither repository contains a built binary, deliberately — no `.exe`, no `.dll`, no object files. A clone builds. That is why installing means building, and why there is no download of a compiled artefact in the repository itself.

The documentation repository holds the **Markdown only**; the HTML and PDF you are reading are generated from it and are not stored there.

Reporting what you find

Open an issue on the server repository — <https://github.com/dmontaine/sd4windows/issues> — for anything about SD itself, and on the documentation repository for an error in these pages. If you are not sure which, the server one is the right guess.

Issues rather than pull requests. Both repositories are readable by anyone and **writable only by the author**, so a change cannot be merged from outside; a clear issue is worth more than a patch nobody can apply. A patch attached to an issue is welcome, it just travels that way.

The two things worth reporting in most detail are **anything that behaves differently from OpenQM and is not described here**, and **anything in these pages that turns out not to be true of the build you are running**. The second is as valuable as the first.

Quote the version as `W1.0-0` — the string in the header bar of every page here, in the installer's file name, and in what `sd --version` reports. The bare `1.0-0` is the same release; the `W` says it is the Windows one, and that is the part worth keeping in a report.