
Platform staff guide


Who this is for: NestSelf staff who work in NestSelf Admin. The pictures show fictional sample people.

Sign in


1. Open NestSelf Admin, type your work email address and press **Continue**.



2. Type your password and press **Sign in**.




3. The first time, scan the QR code with your authenticator app, type the code it shows and press **Confirm setup**.



The QR code and the key are hidden in this picture.


4. Every other time, type the code from your authenticator app and press **Verify**.




If it fails: "The code you entered is not valid." Wait for the next code in the app and type it.

Clients and users


1. Choose **Organisations** and open the client.




2. Open **People** to see the members and end a membership.




3. Open **Access** to assign or revoke templates and transfer ownership.




4. To check a user, choose **Access** in the menu, type the user ID under **User access** and press **Look up**.



5. To suspend that user, press **Suspend user**, type the reason and press **Suspend user**.




6. To lift a suspension, look the user up, press **Reinstate user** and press **Reinstate user** again.




Emergency access


1. Choose **Emergency access**, press **Request access**, write the purpose, choose **Case** or **Person's records** and type its ID, choose the **Duration** and press **Send request**.




2. If **Verify your identity** opens, type the code NestSelf emailed you and press **Verify**.




3. Ask another staff member to press **Approve** on your request and confirm.



4. When your request shows **Active**, press **Open record**.




5. Choose the **Record type**, type the record ID and press **Read record**.




Single sign-on for a client

1. Choose **SSO**, press **New connection**, find the organisation, choose the protocol, type a slug, fill in the provider details from the client and press **Create connection**.




If it fails: "Another organisation already uses this slug for its SSO connection. Choose a different slug."

2. Press **Details** on the new connection.




3. Press **Add domain**, type the client's email domain and press **Add domain**.




If it fails: "Public email domains such as gmail.com cannot be used for SSO. Use the employer's own domain."

4. Send the client the **Record name** and **Record value** to publish in their DNS, and press **Done**.




The record value is hidden in this picture.

5. Send the client the **Entity ID** and **ACS URL** for their identity provider; the domain waits as **Pending** with its record.




The record value is hidden in this picture.

6. When the client has published the record, press **Verify** next to the domain.




If it fails: "The DNS TXT record was not found or does not match. Check the record name and value, or wait for DNS to update, and try again."

7. Press **Test sign-in**, then open the link in a new tab or send it to the client's tester, an invited person with an address on the verified domain.



Part of the link is hidden in this picture.


8. When the test sign-in has finished, press **Activate**; the connection shows **Active**.




If it fails: "Complete a test sign-in on a verified domain before activating the connection." Run the test sign-in again.

Suspend or reset a connection

1. Press **Suspend** and confirm to stop sign-in through the client's provider; **Reactivate** restarts it.



2. Press **Reset to draft** and confirm to start a connection in testing over.




What to tell the client about `email_verified`

Ask whether their OIDC sign-in sends `email_verified` (Entra ID does not by default). If it does not, leave **Require a verified email claim from the provider** on: each employee then confirms their address once with a code NestSelf sends them. Turn it off (**Edit**) only after the client confirms in writing that the email their sign-in sends is their directory's verified address.

Verify your identity

1. When **Verify your identity** opens as you suspend or reinstate a user, end a membership, change access, or open or change SSO connections more than 30 minutes since you signed in or last verified your identity, type the code NestSelf emailed you and press **Verify**.



   If it fails: "The code you entered is not valid." Type the code from the newest email, or press **Send a new code**.

2. Press **Cancel** instead to leave the change undone. On the **SSO** page the connections then stay hidden until you press **Try again** and verify.