

Trend Micro Vision One™

Endpoint Security Configuration & Hardening Playbook

This playbook details the implementation of foundational security controls, active scan rules, and tamper-protection parameters within the **Standard Endpoint Protection Manager (SEP)** console of Trend Micro Vision One.

Control Domain	Target Setting / Parameter	Policy Objective
Anti-Malware Scans	Real-time USB Boot Sector Scanning	Removable Media Defense
Scheduled Scans	Weekly Recurrence: Mondays at 19:00 (7:00 PM)	Routine Compliance Scan
Agent Architecture	Update Agent Role: "Domain Settings" enabled	Distributed Infrastructure
Tamper Protection	Unload & Uninstallation Passwords set to EDu45auni@123456	Local Administrator Override Prevent

Phase 1: Real-Time Threat Mitigation (USB Protection)

Prevents initial access and execution vectors originating from localized physical hardware interfaces upon device mapping.

1. Expand the **Endpoint Security** module in the primary left navigation workspace tree.
2. Select **Endpoint Security Configuration** to drill down into active policy containers.
3. Click on **Standard Endpoint Protection** under the active management sub-tree.
4. Navigate to the **Policies** tab, select your target workspace profile (e.g., **genetech**), and choose to modify its parameters.
5. Under the *Anti-Malware Scans* operational sub-menu, select **Real-time Scan**.
6. Locate the **Scan Settings** contextual panel and firmly ensure the checkbox for "**Scan the boot sector of the USB storage device after plugging in**" is explicitly enabled.
7. Commit settings using the global blue **Save** action button.

Phase 2: Routine Compliance Scanning Engine Schedule

Establishes standard deep analysis workflows during off-peak windows to scrub latent assets on local disk areas.

1. Inside your active operational policy profile editor, navigate to the **Scheduled Scan** configurations tree.

2. Ensure you are modifying parameters directly inside the focused **Target** control tab.
3. Under the **Schedule** selection block, toggle the system selector to **Weekly, every**.
4. Use the operational dropdown menu adjacent to the selection toggle to select **Monday**.
5. Modify the **Start time** inputs to target 7:00 PM evening deployment using standard 24-hour network notation:
 - Set the hour (**hh**) selector index to: **19**
 - Set the minutes (**mm**) selector index to: **00**

CRITICAL TIMING ENFORCEMENT NOTE

Avoid mapping this to standard AM hours (**07:00**) to prevent severe system I/O exhaustion, endpoint resource contention, and user performance degradation during corporate sign-on windows.

Phase 3: Distributed Update Agent Infrastructure Role

Appoints local nodes to act as regional repositories, alleviating raw WAN boundaries and internet breakout bottlenecks.

1. Scroll down through the policy dashboard options directly into the **AGENT CONFIGURATIONS** block and select **Update Agent**.
2. Under the primary workspace statement "*Security Agents can act as Update Agents for:*", mark the active checkbox for **Domain settings**.
3. Review any additional operational components required for synchronization (such as active signatures or engine binaries).

UPSTREAM COALESCENCE STEP REQUIRED

This is a linked two-stage configuration framework. To finish optimization, log into the downstream **Apex One web console** and path directly via **Updates > Agents > Update Sources** to map target organizational units to this newly created local provider.

Phase 4: Tamper Protection & Enforcement Mechanics

Introduces protective friction boundaries to stop localized administrative escalation or unauthorized removal of the client agent.

1. From the left structural module selection pane under *AGENT CONFIGURATIONS*, choose **Privileges and Other Settings**.
2. Locate the **Unload and Unlock** configuration banner area:
 - Enable the explicit requirement radio button: **Requires a password:**
 - Type the strong administrative key value **EDu45auni@123456** into the matching password field boxes.

3. Descend slightly to locate the adjacent **Uninstallation** structural control layer:
 - Enable the operational safety radio button: **Requires a password:**
 - Input the structural enforcement key code **EDu45auni@123456** inside the designated text areas.
4. Finalize all configurations by saving the policy tree to deploy updates globally.