

Accessing Mission Control From Your Phone

OpenClaw Masterclass — Phone Access Guide

Why this matters

You've built a full Mission Control dashboard, but up until now you've only been opening it on your laptop. This guide shows you how to access it from your phone so you can check in on your agents, add tasks, and review your morning briefing from anywhere.

Pick your path

There are three ways to access Mission Control from your phone depending on your setup. Use the one that matches you:

Your Setup	Go To
You already installed Tailscale earlier in the course (VPS users or local users who followed along)	Path A — Tailscale Phone Access
You're running OpenClaw locally on your computer and you want to access it from your phone at home	Path B — Local Network Access
You're local, you don't have Tailscale yet, but you want proper access from anywhere	Path C — Install Tailscale Now

Path A: Tailscale Phone Access

For anyone who already has Tailscale installed (from the Tailscale lesson in Section 7).

This is the simplest method. You just add your phone to the same Tailscale network as your computer or VPS, and you can access Mission Control from anywhere with an internet connection.

Step 1: Install Tailscale on your phone

iPhone: Open the App Store, search for "Tailscale", install the app.

Android: Open Google Play Store, search for "Tailscale", install the app.

Step 2: Log in with the same account

Open the app and log in using the same account you used when setting up Tailscale on your VPS or computer. This is the important bit — your phone needs to be on the same Tailscale network as Mission Control.

Step 3: Connect

Hit the Connect toggle in the app. You should see your phone listed as connected. That's it — your phone is now part of your private Tailscale network.

Step 4: Find your Tailscale IP

You need the Tailscale IP of the machine running Mission Control. It looks like 100.x.x.x. You can find it by:

- Asking your agent: "what's my Tailscale IP?"
- Checking the Tailscale admin panel on your laptop
- Opening the Tailscale app on your computer

Step 5: Open Mission Control on your phone

In your phone browser, type the URL in this format:

```
http://YOUR_TAILSCALE_IP:3007
```

For example: `http://100.67.190.10:3007`

Mission Control should load on your phone. You can scroll through the sidebar, open the Task Board, check the Calendar, view the Office — everything works.

Tip: Add the URL to your home screen

On iPhone, tap the share button and choose "Add to Home Screen". On Android, tap the menu and "Add to Home screen". Now you've got Mission Control as an app icon on your phone.

What to expect

This works from anywhere — home WiFi, mobile data, a cafe, a train, another country. As long as your phone has internet and Tailscale is connected, you can pull up Mission

Control. It's secure because only devices on your Tailscale network can access it.

Path B: Local Network Access

For local users without Tailscale who just want phone access at home on the same WiFi.

If you're running OpenClaw on your own computer and you just want to access Mission Control from your phone while you're at home, you can do it directly through your local WiFi network. No Tailscale, no extra setup.

Step 1: Find your computer's local IP address

Your computer has a local IP on your home network that looks something like 192.168.1.50. Here's how to find it:

On Mac: Open Terminal and run:

```
ipconfig getifaddr en0
```

On Windows: Open Command Prompt and run:

```
ipconfig
```

Look for the IPv4 Address under your WiFi adapter.

On Linux: Open Terminal and run:

```
hostname -I
```

You'll get an address like 192.168.1.50 or 10.0.0.42. That's your computer's address on the local network.

Step 2: Make sure your phone is on the same WiFi

This method only works when your phone and your computer are on the same WiFi network. Check your phone's WiFi settings to make sure.

Step 3: Open Mission Control on your phone

In your phone browser, type the URL in this format:

```
http://YOUR_LOCAL_IP:3007
```

For example: `http://192.168.1.50:3007`

Mission Control should load straight up. No login, no tunnel, just a direct connection within your home network.

Limitations

This approach only works when your phone is on the same WiFi as your computer. The moment you leave the house, you won't be able to access Mission Control. If you want access from anywhere, use Path A (Tailscale) or Path C (install Tailscale now).

Path C: Install Tailscale Now

For local users who want proper access from anywhere and haven't set up Tailscale yet.

Tailscale gives all your devices their own private network, so they can talk to each other securely from anywhere. Once you set it up, you can access Mission Control from your phone whether you're at home, at a cafe, or on the other side of the world.

Step 1: Install Tailscale on your computer

Go to tailscale.com and download the installer for your operating system (Mac, Windows, or Linux). Install it, open it, and log in. A free personal account is enough for most users — it supports up to 100 devices.

Step 2: Note your Tailscale IP

Once Tailscale is running on your computer, it assigns it an IP starting with 100. You can see it in the Tailscale menu bar icon or admin panel. It'll look something like 100.67.190.10.

Step 3: Install Tailscale on your phone

iPhone: App Store, search "Tailscale", install.

Android: Google Play Store, search "Tailscale", install.

Log in with the same account you used on your computer.

Step 4: Connect and access Mission Control

Tap Connect in the Tailscale app on your phone. Then open your phone browser and go to:

```
http://YOUR_TAILSCALE_IP:3007
```

Why this is worth doing

Even if you're running OpenClaw locally, installing Tailscale means:

- You can access Mission Control from anywhere, not just at home
- Your connection is secure and private — nothing is exposed to the public internet
- You can add as many devices as you want (laptop, tablet, work computer)
- It's free for personal use up to 100 devices

If you want a fuller walkthrough of Tailscale with screenshots and security considerations, see the Installing Tailscale VPN lesson in Section 7 of the course.

Troubleshooting

Situation	What to do
Page won't load on phone	Check that Tailscale is connected on your phone (Path A/C) or that your phone is on the same WiFi as your computer (Path B).
Wrong IP address	For Tailscale, check your admin panel or the Tailscale app. For local IPs, re-run the command from Step 1 of Path B.
Connection refused	Mission Control might not be running. Tell your agent: "Is Mission Control running on port 3007? If not, restart it."
Works on laptop but not phone	You're probably using the SSH tunnel URL (localhost). Use your Tailscale IP or local IP instead.
Phone shows HTTPS warning	Mission Control runs on HTTP locally. That's normal. Tap "Advanced" and proceed. Or use Path C + Caddy for proper HTTPS.
Slow loading on phone	This can happen on mobile data. Try WiFi first to confirm it's a connection speed issue, not a Mission Control issue.
Want to share with someone else	These paths only work for your own devices. To share with others, see the optional next lesson on public deployment with Caddy.

Quick Reference — URL Formats

Path	URL Format	Example
A Tailscale	http://TAILSCALE_IP:3007	http://100.67.190.10:3007
B Local WiFi	http://LOCAL_IP:3007	http://192.168.1.50:3007
C New Tailscale	http://TAILSCALE_IP:3007	http://100.67.190.10:3007

What's Next

With phone access set up, you can now check in on your Mission Control from anywhere. Add tasks on the go, review your morning briefing with your coffee, show people what you're building.

If you want to go one step further and share your Mission Control with people who aren't on your Tailscale network — clients, team members, anyone — there's an optional bonus lesson coming up on public deployment with Caddy, basic auth, and a proper HTTPS URL.