## expdp -help信息

[oracle@rac01 ~]\$ expdp -help Export: Release 11.2.0.4.0 - Production on Tue Jan 23 10:31:52 2018 Copyright (c) 1982, 2011, Oracle and/or its affiliates. All rights reserved. The Data Pump export utility provides a mechanism for transferring data objects between Oracle databases. The utility is invoked with the following command: Example: expdp scott/tiger DIRECTORY=dmpdir DUMPFILE=scott.dmp You can control how Export runs by entering the 'expdp' command followed by various parameters. To specify parameters, you use keywords: Format: expdp KEYWORD=value or KEYWORD=(value1, value2,..., valueN) Example: expdp scott/tiger DUMPFILE=scott.dmp DIRECTORY=dmpdir SCHEMAS=scott or TABLES=(T1:P1, T1:P2), if T1 is partitioned table USERID must be the first parameter on the command line. The available keywords and their descriptions follow. Default values are listed within square brackets. ATTACH Attach to an existing job. For example, ATTACH=job name. CLUSTER Utilize cluster resources and distribute workers across the Oracle RAC. Valid keyword values are: [Y] and N. COMPRESSION Reduce the size of a dump file. Valid keyword values are: ALL, DATA\_ONLY, [METADATA\_ONLY] and NONE. Specifies data to unload. Valid keyword values are: [ALL], DATA\_ONLY and METADATA\_ONLY. DATA\_OPTIONS Data layer option flags. Valid keyword values are: XML CLOBS. DIRECTORY Directory object to be used for dump and log files. DUMPFILE Specify list of destination dump file names [expdat.dmp]. For example, DUMPFILE=scott1.dmp, scott2.dmp, dmpdir:scott3.dmp. ENCRYPTION Encrypt part or all of a dump file. Valid keyword values are: ALL, DATA\_ONLY, ENCRYPTED\_COLUMNS\_ONLY, METADATA\_ONLY and NONE. ENCRYPTION ALGORITHM Specify how encryption should be done. Valid keyword values are: [AES128], AES192 and AES256. ENCRYPTION\_MODE Method of generating encryption key. Valid keyword values are: DUAL, PASSWORD and [TRANSPARENT]. ENCRYPTION PASSWORD Password key for creating encrypted data within a dump file. ESTIMATE Calculate job estimates. Valid keyword values are: [BLOCKS] and STATISTICS. ESTIMATE ONLY Calculate job estimates without performing the export. EXCLUDE Exclude specific object types.

For example, EXCLUDE=SCHEMA: "='HR'".

FILESIZE

Specify the size of each dump file in units of bytes. FLASHBACK SCN SCN used to reset session snapshot. FLASHBACK\_TIME Time used to find the closest corresponding SCN value. FULL Export entire database [N]. HELP Display Help messages [N]. INCLUDE Include specific object types. For example, INCLUDE=TABLE DATA. Name of export job to create. LOGFILE Specify log file name [export.log]. NETWORK LINK Name of remote database link to the source system. NOLOGFILE Do not write log file [N]. PARALLEL Change the number of active workers for current job. PARFILE Specify parameter file name. QUERY Predicate clause used to export a subset of a table. For example, QUERY=employees: "WHERE department\_id > 10". REMAP\_DATA Specify a data conversion function. For example, REMAP DATA=EMP. EMPNO: REMAPPKG. EMPNO. REUSE DUMPFILES Overwrite destination dump file if it exists [N]. SAMPLE Percentage of data to be exported. SCHEMAS List of schemas to export [login schema]. SERVICE\_NAME Name of an active Service and associated resource group to constrain Oracle RAC resources. SOURCE EDITION Edition to be used for extracting metadata. Frequency (secs) job status is to be monitored where the default [0] will show new status when available. TABLES Identifies a list of tables to export. For example, TABLES=HR. EMPLOYEES, SH. SALES: SALES\_1995. TABLESPACES Identifies a list of tablespaces to export. TRANSPORTABLE Specify whether transportable method can be used. Valid keyword values are: ALWAYS and [NEVER]. TRANSPORT FULL CHECK Verify storage segments of all tables [N]. TRANSPORT\_TABLESPACES

List of tablespaces from which metadata will be unloaded.

Valid keyword values are: [COMPATIBLE], LATEST or any valid database version.

VERSION

Version of objects to export.

The following commands are valid while in interactive mode.

Note: abbreviations are allowed.

ADD\_FILE

Add dumpfile to dumpfile set.

CONTINUE\_CLIENT

Return to logging mode. Job will be restarted if idle.

EXIT CLIENT

Quit client session and leave job running.

FILESIZE

Default filesize (bytes) for subsequent ADD\_FILE commands.

HELP

Summarize interactive commands.

KILL\_JOB

Detach and delete job.

PARALLEL

Change the number of active workers for current job.

REUSE\_DUMPFILES

Overwrite destination dump file if it exists [N].

START\_JOB

Start or resume current job.

Valid keyword values are: SKIP\_CURRENT.

STATUS

Frequency (secs) job status is to be monitored where the default [0] will show new status when available.

STOP JOB

Orderly shutdown of job execution and exits the client.

Valid keyword values are: IMMEDIATE.

[oracle@rac01 ~]\$