create or replace procedure p_db_mantainace_v21

```
create or replace procedure p_db_mantainace_v21 as
  Type EmpCurTyp Is Ref Cursor;
  stmtCursor EmpCurTyp;
         Varchar2(1000);
  stmt
begin
    Open stmtCursor For
 select 'alter table QZJ_INTERFACE_V21.' || tab_code ||' enable row movement'
    from QZJ_ETL_V21.SYS_TABLE_LIST
    order by TAB_SNO;
 1oop
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt;
 End Loop;
    Close stmtCursor;
 Open stmtCursor For
 select 'alter table QZJ_NORM_V21.' || tab_code || ' enable row movement'
   from QZJ ETL V21. SYS TABLE LIST
   order by TAB_SNO;
  1oop
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt;
 End Loop;
    Close stmtCursor;
 Open stmtCursor For
 select 'alter table QZJ_NORM_V21.' \mid \mid tab_code \mid \mid ' shrink space'
   from QZJ_ETL_V21.SYS_TABLE_LIST
   where TAB USED = 1
   order by TAB SNO;
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt;
 End Loop;
    Close stmtCursor;
 Open stmtCursor For
 select 'alter table QZJ_INTERFACE_V21.' || tab_code || ' shrink space'
    from QZJ_ETL_V21.SYS_TABLE_LIST
    where TAB USED = 1;
  Loop
    Fetch stmtCursor Into stmt;
    Exit When stmtCursor%Notfound;
    dbms_output.put_line(stmt);
    execute immediate stmt;
 End Loop;
    Close stmtCursor;
```

```
Open stmtCursor For
 select 'alter index ' || owner || '.' || index_name ||
       ' rebuild nologging parallel 4'
    from all_indexes
    where owner in ('QZJ_NORM_V21', 'QZJ_INTERFACE_V21')
    order by index_name, owner;
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt:
 End Loop;
    Close stmtCursor;
end;
or
create or replace procedure p_db_mantainace_v21 as
  Type EmpCurTyp Is Ref Cursor;
  stmtCursor EmpCurTyp;
        Varchar2(1000);
  stmt
begin
    Open stmtCursor For
 select 'alter table QZJ_INTERFACE_V21.' || tab_code ||' enable row movement'
    from QZJ_ETL_V21.SYS_TABLE_LIST
 union
    select 'alter table QZJ_NORM_V21.' || tab_code || ' enable row movement'
   from QZJ_ETL_V21.SYS_TABLE_LIST;
 100p
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt;
 End Loop;
    Close stmtCursor;
 Open stmtCursor For
 select 'alter table QZJ_NORM_V21.' || tab_code || ' shrink space'
   from QZJ_ETL_V21.SYS_TABLE_LIST
   where TAB\_USED = 1
  union
  select 'alter table QZJ_INTERFACE_V21.' || tab_code || ' shrink space'
    from QZJ_ETL_V21.SYS_TABLE_LIST
    where TAB USED = 1;
  Fetch stmtCursor Into stmt;
  Exit When stmtCursor%Notfound;
  dbms_output.put_line(stmt);
  execute immediate stmt;
 End Loop;
    Close stmtCursor;
```