## oracle 10g 研究ORACLE\_HOME rdbms admin 下的脚本的功能 (17) awrload.sql

oracle 10g 研究ORACLE\_HOME rdbms admin 下的脚本的功能 (17) awrload.sql

```
#AWR LOAD
#SQL/Plus script to help users load data into the AWR from
        a dump file.
Rem $Header: awrload.sql 06-apr-2005.18:35:13 mlfeng Exp $
Rem
Rem awrload. sql
Rem
Rem Copyright (c) 2004, 2005, Oracle. All rights reserved.
Rem
Rem
        awrload.sql - AWR LOAD
Rem
Rem
      DESCRIPTION
        SQL/Plus script to help users load data into the AWR from
Rem
        a dump file.
Rem
Rem
Rem
Rem
        User must be connected as SYS to run this SQL/Plus script.
Rem
      MODIFIED (MM/DD/YY)
Rem
Rem
      mlfeng
              03/01/05 - add disclaimer for support, create staging
Rem
      mlfeng
                 06/01/04 - mlfeng_awr_import_export
              05/17/04 - Created
      mlfeng
Rem
-- Use the default directory name, file name, schema
-- define directory_name = 'DATA_PUMP_DIR'
                    = 'awrdat'
-- define file_name
-- define schema name = 'AWR STAGE'
-- define default tablespace = ''
-- define temporary_tablespace = ''
set echo off heading on underline on verify off
set feedback off linesize 80 termout on;
whenever sqlerror exit;
prompt Disclaimer: This SQL/Plus script should only be called under
                  the guidance of Oracle Support.
prompt
prompt
prompt ~~~~~~
prompt AWR LOAD
prompt ~~~~~~
prompt \tilde{\ } This script will load the AWR data from a dump file. The
```

```
prompt \tilde{\ } script will prompt users for the following information:
prompt ~
             (1) name of directory object
prompt
             (2) name of dump file
prompt ~
             (3) staging schema name to load AWR data into
prompt
-- Ask User for Directory Name
prompt
prompt Specify the Directory Name
prompt ~~~~~~~~~~~~
set heading on;
column dirname format a30 heading 'Directory Name'
column dirpath format a49 heading 'Directory Path'
select directory_name dirname, directory_path dirpath
  from DBA_DIRECTORIES
 order by directory name;
set termout off;
column dflt_dir new_value dflt_dir noprint;
select '' dflt_dir from dual;
set termout on;
prompt Choose a Directory Name from the list above (case-sensitive).
prompt
set heading off;
column directory_name new_value directory_name noprint;
select 'Using the dump directory: ' \mid\mid nvl('&&directory_name','&dflt_dir')
     , nv1('&&directory_name','&dflt_dir') directory_name
  from sys. dual;
variable dmpdir varchar2(30);
variable dmppath varchar2(4000)
declare
  cursor dirpath (dirname varchar2) is
    select directory_path
      from dba_directories
      where directory_name = dirname;
begin
  :dmpdir := '&directory_name';
   /* select the directory path into a variable */
   open dirpath(:dmpdir);
   fetch dirpath into :dmppath;
   if (dirpath%NOTFOUND) then
     RAISE_APPLICATION_ERROR (-20103,
```

```
'directory name ''' || :dmpdir ||
                              ''' is invalid', TRUE);
   end if;
  close dirpath;
end;
set termout off;
column dflt_name new_value dflt_name noprint;
select '' dflt name from dual;
set termout on;
prompt
prompt Specify the Name of the Dump File to Load
prompt Please specify the prefix of the dump file (.dmp) to load:
prompt
set heading off;
column file name new value file name noprint;
select 'Loading from the file name: ' || nv1('&&file_name','&dflt_name')
       || '.dmp'
      , nvl('&&file_name','&dflt_name') file_name
  from sys.dual;
variable dmpfile \ varchar2(30);
begin
  :dmpfile := '&file_name';
end;
set termout off;
column dflt_schema new_value dflt_schema noprint;
select 'AWR_STAGE' dflt_schema from dual;
set termout on;
prompt
prompt Staging Schema to Load AWR Snapshot Data
prompt The next step is to create the staging schema
prompt where the AWR snapshot data will be loaded.
prompt After loading the data into the staging schema,
prompt the data will be transferred into the AWR tables
prompt in the SYS schema.
prompt
prompt
prompt The default staging schema name is &dflt_schema..
prompt To use this name, press <return> to continue, otherwise enter
prompt an alternative.
prompt
set heading off;
column schema_name new_value schema_name noprint;
select 'Using the staging schema name: ' | \ | \ | nv1('&&schema_name','&dflt_schema')
     , nvl('&&schema_name','&dflt_schema') schema_name
```

```
from sys.dual;
variable schname varchar2(30);
variable schoount number;
/* check if schema already exists */
declare
  cursor schemas (schname varchar2) is
    select count(*) schcount
      from dba_users
     where username = schname
      order by username:
begin
  :schname := '&schema_name';
  /* select the directory path into a variable */
  open schemas(:schname);
   fetch schemas into :schcount;
   if (:schcount > 0) then
     RAISE_APPLICATION_ERROR(-20104,
                             'schema name ''' || :schname ||
                              ''' already exists', TRUE);
   end if:
   close schemas;
end;
prompt
prompt Choose the Default tablespace for the &schema_name user
prompt Choose the &schema_name users's default tablespace. This is the
prompt tablespace in which the AWR data will be staged.
set heading on
column db_default format a18 heading 'DEFAULT TABLESPACE'
select\ tablespace\_name, contents
     , decode(tablespace_name,'SYSAUX','*') db_default
  from sys.dba_tablespaces
where tablespace_name <> 'SYSTEM'
  and contents = 'PERMANENT'
  and status = 'ONLINE'
order by tablespace_name;
set heading off
prompt
prompt Pressing <return> will result in the recommended default
prompt tablespace (identified by *) being used.
prompt
col default_tablespace new_value default_tablespace noprint
select 'Using tablespace '||
       upper(nv1('&&default_tablespace','SYSAUX'))||
       ' as the default tablespace for the &&schema_name.'
     , nvl('&default_tablespace','SYSAUX') default_tablespace
```

```
begin
  if upper('&&default_tablespace') = 'SYSTEM' then
    raise_application_error(-20105, 'Load failed - SYSTEM tablespace ' \mid \mid
                                    'specified for DEFAULT tablespace');
  end if;
end;
prompt
prompt
prompt Choose the Temporary tablespace for the &&schema_name user
prompt Choose the &schema_name user's temporary tablespace.
set heading on
column db_default format a23 heading 'DEFAULT TEMP TABLESPACE'
select t.tablespace_name, t.contents
     , decode(dp.property_name, 'DEFAULT_TEMP_TABLESPACE', '*') db_default
  from sys.dba_tablespaces t
     , sys.database_properties dp
 where t. contents = 'TEMPORARY'
                           = 'ONLINE'
  and t. status
  and dp. property_name(+) = 'DEFAULT_TEMP_TABLESPACE'
  and dp. property_value(+) = t. tablespace_name
order by tablespace_name;
set heading off
prompt
prompt Pressing <return> will result in the database's default temporary
prompt tablespace (identified by *) being used.
prompt
col temporary_tablespace new_value temporary_tablespace noprint
select 'Using tablespace '||
       nvl('&&temporary_tablespace', property_value)||
       ' as the temporary tablespace for &&schema_name.'
     , nvl('&&temporary_tablespace',property_value) temporary_tablespace
  from database_properties
 where property_name='DEFAULT_TEMP_TABLESPACE';
begin
  if upper('&&temporary_tablespace') = 'SYSTEM' then
    raise_application_error(-20106, 'Load failed - SYSTEM tablespace ' ||
                                    'specified for TEMPORARY tablespace');
  end if;
end;
set heading off
prompt
prompt
prompt ... Creating &&schema_name user
```

from sys.dual;

```
create user &&schema_name
  identified by &&schema_name
  default tablespace &&default tablespace
  temporary tablespace &&temporary_tablespace;
alter user &&schema_name quota unlimited on &&default_tablespace;
prompt
set termout on;
set serveroutput on;
exec dbms_output.enable(500000);
set termout on;
            format a80 newline;
column loc
column locend format a80;
declare
 begpos NUMBER;
  numchar NUMBER := 74;
begin
  dbms_output.put_line('|');
 dbms_output.put_line(' | Loading the AWR data from the following ');
  dbms_output.put_line(' | directory/file:
 begpos := 1;
  WHILE (begpos <= length(:dmppath)) LOOP
   dbms_output.put_line(' | ' | | substr(:dmppath, begpos, numchar));
   begpos := begpos + numchar;
  END LOOP;
  dbms_output.put_line(' | ' | | :dmpfile | | '.dmp');
  dbms_output.put_line('|
  dbms_output.put_line('|');
  dbms_output.put_line(' | *** AWR Load Started ...');
  dbms_output.put_line('|');
  dbms_output.put_line(' | This operation will take a few moments. The ');
  dbms_output.put_line(' | progress of the AWR load operation can be ');
  dbms_output.put_line(' | monitored in the following directory/file: ');
 begpos := 1;
  WHILE (begpos <= length(:dmppath)) LOOP
   dbms_output.put_line('| ' || substr(:dmppath, begpos, numchar));
   begpos := begpos + numchar;
  END LOOP;
 dbms_output.put_line(' | ' | | :dmpfile | | '.log');
  dbms output.put line('|');
end;
whenever sqlerror continue;
set heading off;
set linesize 110 pagesize 50000;
set echo off;
```

```
set feedback off;
set termout on;
begin
  /\!\!* call PL/SQL routine to load the data into the staging schema *\!/
  {\tt dbms\_swrf\_internal.\,awr\_load(schname} \ \ \Rightarrow \ : schname,
                               dmpfile => :dmpfile,
                               dmpdir => :dmpdir);
end;
begin
  /* call PL/SQL routine to move the data into AWR */
  dbms_swrf_internal.move_to_awr(schname => :schname);
end;
prompt ... Dropping &&schema_name user
drop user &&schema_name cascade;
prompt
prompt End of AWR Load
undefine directory_name
undefine file_name
undefine schema_name
undefine default_tablespace
undefine temporary_tablespace
```