

RAINFALL AT Morwenstow Yeanage

Lat. 50° 55'

Lon. 4° 30' W. County of Cornwall

Horrido Rain Gauge, by A & H Stiles Observer Revd H Lynne Jones

Barrel & N. in lowest streams —

Diameter ..						5					
Height ..						9.10					
Altitude ..						381	N				
Year	1900	1901	1902	1903	1904	1905	1906	1907	1908	1909	MEANS.
January ..							5.94	1.80	1.86	2.21	
February ..							4.35	1.49	2.62	.54	
March							2.18	1.09	3.39	3.95	
April							1.96	4.80	2.36	2.39	
May							4.20	3.87	1.56	1.45	
June							1.29	3.59	.95	1.71	
July							2.03	2.05	2.67	3.04	
August							3.95	2.29	3.25	3.59	1.50
September ..							1.80	1.27	1.17	2.78	2.08
October ...							1.95	6.10	7.96	2.10	6.87
November ..							4.30	5.10	3.80	2.35	1.60
December ..							2.05	3.28	4.86	4.77	5.04
TOTALS ..							39.99	39.73	30.90	32.38	

1906 Morwenstow Church 60 yards S.W.

Bude Station 10 miles S

Home 35 ft high 90 ft NE

Trees 45 - " 90 " S.S.W.

RAINFALL at Morwenstow Vicarage

County of Cornwall

Observer Rev H. Y. Jones

River Basin Camel + NW Coast streams

Harold Rain Gauge, by Arrows & Slope

Diameter ...	5										
Height	0 10										
Altitude ...	331 ft										
Year ...	1910	1911	1912	1913	1914	1915	1916	1917	1918	1919	MEANS.
January ...	3.69	2.00	3.73	5.44	1.60	3.35	1.98	1.60	4.58	5.64	
February ...	4.16	2.68	2.60	1.29	4.31	5.39	7.10	2.50	2.89	3.80	
March69	2.89	6.45	5.16	6.05	1.00	3.58	3.49	1.89	4.45	
April	2.47	2.38	.38	3.70	1.58	1.60	1.04	1.86	2.16	2.26	
May	2.56	1.69	1.72	3.60	1.46	2.94	1.91	2.36	1.10	1.93	
June.....	2.63	3.62	7.39	1.84	2.46	2.02	2.63	5.23	1.55	1.14	
July	2.62	.50	4.25	.62	5.55	4.89	1.01	3.34	4.81	.95	
August.....	2.07	3.19	7.96	1.98	4.51	2.01	1.96	5.73	3.61	2.75	
September ..	.29	3.21	.79	2.80	2.65	2.01	2.23	2.45	9.02	1.70	
October ...	5.80	3.61	4.87	3.82	2.52	4.83	5.96	5.45	3.27	2.03	
November ..	6.39	4.97	3.87	4.42	4.20	2.85	4.63	2.85	3.76	4.62	
December...	5.63	6.89	6.91	3.29	6.33	7.47	4.18	1.06	6.15	6.60	
TOTALS ...	40.00	37.63	50.92	37.96	43.22	40.36	38.11	37.92	44.79	37.87	

1910 June 45° N 15° 90° E SSW
House 35° 90° NE

Date.	Lat. N.	Long.	Railway Station.	Distance.	Direction.	Church.	Distance.	Direction.
1910	50 55	4 30 W	Bude	10 miles	S	Morwenstow	60 yds	S W

RAINFALL at Morwenstow Vicarage

County of Cornwall

Observer Rev. S. Lyne-Jones.

River Basin

1

(after Sept 10th 1923) Rev. H. Hugh Breton, M.A.

Howard Rain Gauge, by A. Goldthorpe.

Diameter ...	5"					8"					
Height	0.10					1.0					
Altitude ...	331										
Year	1920	1921	1922	1923	1924	1925	1926	1927	1928	1929	MEANS.
January ...	5.73	4.54	3.86	1.75	5.46	3.39	6.45	6.72			
February ...	1.26	.51	4.12	7.20	1.43	6.37	4.28	3.51			
March	4.81	3.77	3.08	1.34	2.38	.67	.78	5.00			
April	4.30	.98	3.34	2.38	3.52	3.06	1.98				
May	2.75	1.72	2.15	1.77	3.22	5.72	2.17				
June	2.02	.05	1.41	1.17	1.89	.00	1.64				
July	5.68	1.55	3.09	2.91	5.04	4.04	2.61				
August	2.48	2.98	2.99	2.46	4.61	6.11	3.39				
September...	4.18	1.89	2.67	3.76	4.70	3.91	1.44				
October....	5.24	1.64	1.62	6.56	6.57	5.00	3.29				
November...	2.74	3.50	1.72	4.30	3.42	3.30	8.83				
December...	2.45	2.93	5.45	4.77	5.32	4.70	1.37				
TOTALS...	57.14	26.06	35.50	40.37	47.56	46.33	38.23				
	0	0	0	0	0	0	0				

1920 gauge 55 ft. 90 ft. off. N.E.
 3102.45 ft. 45 ft. 30 ft. S.W.

1921 Gauge to Dean Prior after March.
 S. Devon 1/4

Position of Station on reduced Ordnance Survey Map, 2 miles to 1 inch Series } No. of Map _____ Reference No. _____

Date.	Lat. N.	Long.	Railway Station.	Distance from gauge	Direction from gauge	Parish Church.	Distance from gauge	Direction from gauge
1920.	50°55'	4°30' w.	Bude	10 miles	s.	Morwenstow.	60 yds.	s.w.