Creación entorno virtual:

Se crean las carpetas en el directoria asignado:

Activar el entorno virtual:

```
Símbolo del sistema                                          —  □  ×

Microsoft Windows [Versión 10.0.19043.1526]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\Users\52557>cd..

C:\Users>cd..

C:\>python -m venv C:\Users\52557\Documents\entorno_virtual

C:\>C:\Users\52557\Documents\entorno_virtual\scripts\activate
```

Ver librerías:

```
Símbolo del sistema                                          —  □  ×

Microsoft Windows [Versión 10.0.19043.1526]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\Users\52557>cd..

C:\Users>cd..

C:\>python -m venv C:\Users\52557\Documents\entorno_virtual

C:\>C:\Users\52557\Documents\entorno_virtual\scripts\activate

(entorno_virtual) C:\>pip freeze
```

Instalar una librería:

```
(c) Microsoft Corporation. Todos los derechos reservados.

C:\Users\52557>cd..

C:\Users>cd..

C:\>python -m venv C:\Users\52557\Documents\entorno_virtual

C:\>C:\Users\52557\Documents\entorno_virtual\scripts\activate

(entorno_virtual) C:\>pip freeze

(entorno_virtual) C:\>pip install python-dateutil
```



```
Símbolo del sistema                                                    —    □    ×

Microsoft Windows [Versión 10.0.19043.1526]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\Users\52557>cd..

C:\Users>cd..

C:\>python -m venv C:\Users\52557\Documents\entorno_virtual

C:\>C:\Users\52557\Documents\entorno_virtual\scripts\activate

(entorno_virtual) C:\>pip freeze

(entorno_virtual) C:\>pip install python-dateutil
Collecting python-dateutil
  Using cached python_dateutil-2.8.2-py2.py3-none-any.whl (247 kB)
Collecting six>=1.5
  Using cached six-1.16.0-py2.py3-none-any.whl (11 kB)
Installing collected packages: six, python-dateutil
Successfully installed python-dateutil-2.8.2 six-1.16.0
WARNING: You are using pip version 21.2.4; however, version 22.0.3 is available.
You should consider upgrading via the 'C:\Users\52557\Documents\entorno_virtual\Scripts\python.exe -m pip install --upgr
ade pip' command.

(entorno_virtual) C:\>
```

Desactivar entorno virtual: