



Atribuindo endereço de IP no GNU/LINUX:

```
root@server:/home/user#  
root@server:/home/user# S='Verificar IP do S.O'  
root@server:/home/user# ip address  
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000  
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00  
    inet 127.0.0.1/8 scope host lo  
        valid_lft forever preferred_lft forever  
    inet6 ::1/128 scope host noprefixroute  
        valid_lft forever preferred_lft forever  
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000  
    link/ether 08:00:27:50:2a:46 brd ff:ff:ff:ff:ff:ff  
    inet 10.0.2.15/24 brd 10.0.2.255 scope global dynamic noprefixroute enp0s3  
        valid_lft 86242sec preferred_lft 86242sec  
    inet6 fe80::a00:27ff:fe50:2a46/64 scope link noprefixroute  
        valid_lft forever preferred_lft forever  
root@server:/home/user#
```


Verificar o endereço IP FIXO e configuração de rede no VirtualBox:



Visualizar o arquivo de configuração da placa de rede (/etc/network/interfaces)



Editar o arquivo de configuração da placa de rede (/etc/network/interfaces)




A terminal window titled 'Terminal' with a timestamp of '17 de mai 14:20'. The window shows the content of the file /etc/network/interfaces. The text is as follows:

```
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).

source /etc/network/interfaces.d/*

# The loopback network interface
auto lo
iface lo inet loopback


auto enp0s3
iface enp0s3 inet static
address 172.16.10.250
netmask 255.255.255.0
network 172.16.10.0
broadcast 172.16.10.255
```



A terminal window titled 'Terminal' with a timestamp of '17 de mai 14:26'. The window shows a series of commands and their outputs, performed as root. The text is as follows:

```
root@server:/home/user#
root@server:/home/user#
root@server:/home/user# S='COMANDO PARA RESTART NAS CONFIGURACOES DE REDE'
root@server:/home/user# systemctl restart networking.service
root@server:/home/user# S='VER CONFIGURAÇÃO DA PLACA DE REDE'
root@server:/home/user# ip address
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000
    link/ether 08:00:27:50:2a:46 brd ff:ff:ff:ff:ff:ff
    inet 172.16.10.250/24 brd 172.16.10.255 scope global enp0s3
        valid_lft forever preferred_lft forever
    inet6 fe80::a00:27ff:fe50:2a46/64 scope link
        valid_lft forever preferred_lft forever
root@server:/home/user#
```

Teste de comunicação entre o servidor GNU/Linux e host cliente.



The screenshot shows two windows side-by-side. The left window is a Linux terminal with the following content:

```
user@server: ~  
inet 127.0.0.1/8 scope host lo  
    valid_lft forever preferred_lft forever  
inet6 ::1/128 scope host noprefixroute  
    valid_lft forever preferred_lft forever  
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel  
    link/ether 08:00:27:50:2a:46 brd ff:ff:ff:ff:ff:ff  
    inet 172.16.10.250/24 brd 172.16.10.255 scope global enp0s3  
        valid_lft forever preferred_lft forever  
    inet6 fe80::a00:27ff:fe50:2a46/64 scope link  
        valid_lft forever preferred_lft forever  
root@server:/home/user#  
root@server:/home/user#  
root@server:/home/user# ping -c 4 172.16.10.100  
PING 172.16.10.100 (172.16.10.100) 56(84) bytes of data:  
64 bytes from 172.16.10.100: icmp_seq=1 ttl=128 time=0.728 ms  
64 bytes from 172.16.10.100: icmp_seq=2 ttl=128 time=0.815 ms  
64 bytes from 172.16.10.100: icmp_seq=3 ttl=128 time=0.504 ms  
64 bytes from 172.16.10.100: icmp_seq=4 ttl=128 time=0.800 ms  
--- 172.16.10.100 ping statistics ---  
4 packets transmitted, 4 received, 0% packet loss, time 3074ms  
rtt min/avg/max/mdev = 0.504/0.711/0.815/0.124 ms  
root@server:/home/user#
```

The right window is a Windows 10 VM titled "Windows 10 - AD [Executando] - Oracle VM VirtualBox". It shows the command prompt with the following content:

```
Arquivo  Máquina  Visualizar  Entrada  Dispositivos  Ajuda  
C:\Windows\system32\cmd.exe  
(c) Microsoft Corporation. Todos os direitos reservados.  
C:\Users\suporte>ipconfig  
Configuração de IP do Windows  
Adaptador Ethernet Ethernet:  
    Sufixo DNS específico de conexão. . . . . :  
    Endereço IPv6 de link local . . . . . : fe80::8586:a159:a47a:98e%14  
    Endereço IPv4. . . . . : 172.16.10.100  
    Máscara de Sub-rede . . . . . : 255.255.255.0  
    Gateway Padrão. . . . . : 172.16.10.1  
C:\Users\suporte>ping 172.16.10.250  
Disparando 172.16.10.250 com 32 bytes de dados:  
Resposta de 172.16.10.250: bytes=32 tempo<1ms TTL=64  
Resposta de 172.16.10.250: bytes=32 tempo<1ms TTL=64  
Resposta de 172.16.10.250: bytes=32 tempo<1ms TTL=64  
Resposta de 172.16.10.250: bytes=32 tempo<1ms TTL=64  
Estatísticas do Ping para 172.16.10.250:  
    Pacotes: Enviados = 4, Recebidos = 4, Perdidos = 0 (0% de  
        perda),  
    Aproximar um número redondo de vezes em milissegundos:  
        Mínimo = 0ms, Máximo = 1ms, Média = 0ms  
C:\Users\suporte>
```

Arquivo de configuração para resolução de nomes (DNS)

```
root@server:/home/user#  
root@server:/home/user# S='Arquivo de resolução de nomes no GNU/LINUX'  
root@server:/home/user# cat /etc/resolv.conf  
#DNS Google  
nameserver 8.8.8.8  
#DNS Embratel  
nameserver 200.255.255.65  
root@server:/home/user#  
root@server:/home/user#
```