




BLKEXPORT User Guide

June 2026

By David Egan

**Software
Version 1.1**

1. Overview

BLKEXPORT is a desktop utility designed to process AutoCAD 2018 ASCII (*.dxf) DXF drawings and identify block insertions. The application categorises blocks into Anonymous Blocks, Non-Attributed Blocks, and Attributed Blocks, then allows the results to be exported to CSV files. It also provides a summarised BOM (Bill of Materials) export and full block schedule export.

2. Software Interface




Figure 1

The main window displays the selected DXF file, categorised block tabs, export options, and an integrity summary showing validation results.

3. Menu Commands

File Menu:

- Open DXF (Ctrl+O) – Open and process a AutoCAD 2018 ASCII (*.dxf) DXF drawing.
- Export to CSV (Ctrl+E) – Export full block schedule data.
- Export BOM to CSV (Ctrl+B) – Export a summarised BOM (Bill of Materials) .
- Exit (Ctrl+X) – Close the application.

Help Menu:

- About – Displays application version and registration information.

4. Loading a DXF File

1. Select File > Open AutoCAD 2018 ASCII (*.dxf) DXF or press Ctrl+O.
2. Browse to the required AutoCAD 2018 ASCII (*.dxf) DXF file.
3. The application processes the drawing and populates the block tables.
4. Review the Integrity Summary to confirm successful processing.

5. Block Categories

Anonymous Blocks – Displays anonymous block references detected in the drawing.

Non-Attributed Blocks – Lists blocks without attributes.

Attributed Blocks – Lists blocks containing attribute values.

6. Data Columns

Typical columns include:

- Handle – Unique entity handle.
- Insertion Coordinate – Block insertion point.
- Drawing Space – Model Space or Paper Space.
- Layout Name – Associated layout.
- Block Name – Name of the inserted block.
- Attribute Value – Attribute content when applicable.

7. Exporting Data

Export to CSV:

1. Load a AutoCAD 2018 ASCII (*.dxf) DXF file.
2. Click Export to CSV or press Ctrl+E.
3. Choose a save location.
4. Open the generated full block schedule CSV in Excel or another spreadsheet application.

Export BOM to CSV:

1. Click Export BOM to CSV or press Ctrl+B.
2. Select a destination folder.
3. Open the generated summarised BOM (Bill of Materials) CSV in Excel or another spreadsheet application.

8. Integrity Summary

The Integrity Summary section provides:

- Drawing name (dxf) and modification date.
- Total block count.
- Anonymous, attributed, and non-attributed block counts.
- LUPREC value used for coordinate precision.
- PASS/FAIL status confirming that detected block counts have been verified.




Figure 2

The About dialog displays version information, platform support, registration details, and access to system information.




Figure 3

10. Troubleshooting

No data displayed:

- Verify the selected file is a valid DXF.
- Ensure the drawing contains block insertions.

Export unavailable:

- Load and process a DXF file first.
- Verify you have write permission to the target folder.

Integrity check failure:

- Re-save the drawing as a supported AutoCAD 2018 ASCII (*.dxf) DXF format and reload it.

11. Keyboard Shortcuts

Ctrl+O – Open AutoCAD 2018 ASCII (*.dxf) DXF

Ctrl+E – Export to CSV

Ctrl+B – Export BOM to CSV

Ctrl+X – Exit

