Winaero

At the edge of tweaking

Advertisement

Disable certain Winkey shortcuts in Windows 10

RECOMMENDED: Click here to fix Windows issues and optimize system performance

In Windows 10, it is possible to disable certain keyboard shortcuts which involve the Win key. If you have a strong reason to disable such a shortcut, let's say to re-assign it to some app or script, here is how it can be done.

ADVERTISEMENT

Here are some shortcuts available in Windows 10 out of the box:

+ D - Minimize all windows. See what the difference is between Win + D (Show Desktop) and Win + M (Minimize All) keyboard shortcuts in Windows.

Windows 10.

₩in + Ctrl + D - creates a new virtual desktop.

win + Tab - manage virtual desktops/open Task View. See the following article for more details: Hotkeys to manage Virtual Desktops in Windows 10 (Task View).

win + A - Open the Action Center to view notifications from the operating system and apps. You can <u>disable this keyboard shortcut and the whole Action</u>

Center if you do not use it.

■ Win + K - Open the Connect flyout. It is useful when you need to connect quickly to some device.

##Win + X - Open the power user menu. This menu has shortcuts to useful administrative tools and system functions. See more details here: <u>Use Win+X</u> menu to manage tasks in Windows 10 faster.

For the full Winkey shortcut reference, see these articles:

- <u>Ultimate list of all Windows keyboard shortcuts with Win keys</u>
- 10 keyboard shortcuts for Windows 10 everyone should know

If you want, you can disable one or several Winkey keyboard shortcuts as follows.


- 1. Open Registry Editor.
- 2. Go to the following Registry key:


HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Explorer\A
dvanced

Using Telegram? Subscribe to the

Tip: You can access any desired Registry Rev with one click.

3. In the right pane, you should create a new string value named **DisabledHotkeys**.






4. Set its value data to the characters of hotkeys you want to disable. Here are a few examples:

Set it to X to disable the hotkey Win + X.

Set it to RX to disable hotkeys Win + X and Win + R.

And so on.

In the screenshot below, I disabled the hotkey Win + E:



5. Restart Explorer or sign out and sign in back to your user account.

That's it. Once this is done, the hotkeys you specified will become disabled and unassigned. You can re-use them in a third party app which allows you to assign global hotkeys.

RECOMMENDED: Click here to fix Windows issues and optimize system performance

Support us

Winaero greatly relies on your support. You can help the site keep bringing you interesting and useful content and software by using these options:

If you like this article, please share it using the buttons below. It won't take a lot from you, but it will help us grow. Thanks for your support!

















Advertisment

blog channel

Author: Sergey Tkachenko

Sergey Tkachenko is a software developer from Russia who started Winaero back in 2011. On this blog, Sergey is writing about everything connected to Microsoft, Windows and popular software. Follow him on Telegram, Twitter, and YouTube. View all posts by Sergey Tkachenko

17 thoughts on "Disable certain Winkey shortcuts in Windows 10"

Good information but I think I will rant a bit

[RANT]

It would really be great if ALL keyboard shortcuts were in one place for editing / deleting including those assigned to shortcuts. I have been dealing with "who owns the printscreen button" issue off and on forever. Usually (in this case) it is between Snagit and Dropbox and there is no good way in dropbox to shut off nor CHANGE the behavior.

[\RANT]

Thanks for everything!

I try disable WIN+W (Windows Ink Workspace in Winows 10.0.14393), it's don't work (already restart explorer and relogin user)

Need use windows police weirkgloekghin hotkeyeribe to the

HKEY LOCAL MACHINE\SOFTWARE\Policies\Microsoft\WindowsInkWorkspac

4	r	٦	
	-	-	

AllowWindowsInkWorkspace DWORD (delete) = enable 0 = disable

I think this hotkey is registered by some other process, not by Explorer.

That's why it cannot be disabled using the mentioned tweak.

Or Microsoft "forgot" in include this keyboard sequence into the key list which can be disabled.

It will be possible to incorporate this tweak in one of the following versions of Winaero Tweaker? (both variants)

Well, I think it is possible.

didn't work for me. tried to disable win+v and win+h AND neither of these worked...any idea why?

It worked on Windows 7. But on Windows 10 it is not.

Ok, it works.

Do you know how to disable Win key combinations with Ctrl and Alt keys? I want to leave Win+D, but disable Win+Alt+D or Win+Ctrl+D (by this key the StrokesPlus is typing me current date-time... it did on Windows7...)
Thank you.

Was this ever answered? is there a way to disable the ctrl key input?

<u>blog channel</u>

This article is years old and still nobody knows? Please, this is the only reference to disabling Win+Ctrl+F I've been able to find anywhere. Even if I never check this site again, someone please respond with the solution so future people in my situation get help.

I've got a solution but it requires 3rd party software.

Install AutoHotKey from their official site. Paste the below config into a text file in an editor of your choice, save it, and append ".ahk" to the filename. Your choice on the filename. I called mine "Windows-Virtual-Desktop-Disable.ahk". Right click on the text file you just created and select "Run Script". Done. Enjoy! You are free to remove any lines that correspond to a shortcut you'd like to keep active.

This won't stop Virtual Desktop from running, but it at least disables the keyboard shortcuts that enable it. I also recommend you right-click your task bar and remove the check-mark from "Show Task View Button". AutoHotKey can be configured to run at startup so that you only have to do this once.

```
#tab::return
; Below line disables WIN+CTRL+D
#^D::return
; Below line disables WIN+CTRL+LEFT-ARROW
#^Left::return
```

```
; Below line disables WIN+CTRL+Right-ARROW #^Right::return
```

I can confirm that works!

; Below line disables WIN+TAB

Using Telegram? Subscribe to the

blog channel!

Thank you so much! It works!

you are actually my hero

Hey

I know this is an old post but I would like to have a thing clarified that I cannot find anywhere.

When using this string "DisabledHotkeys" I would like to disable Win + Spacebar (change keyboard input shortcut) but there is no way I can find to tell it it is spacebar I mean, (it takes it as a black entry)

Normal keys such as E R or 1234 are easy enough but spacebar I cannot figure out how to specify.

Thanks – Morten

After creating the "DisabledHotkeys" registry how do I disable the Virtual Desktop keybind (WIN + TAB)??

I've right clicked the entry and clicked "Modify" but I'm not sure how to represent the TAB button??

