Getting the Safe Area

`var safeAreaInsets: UIEdgeInsets`

The insets that you use to determine the safe area for this view.

`var safeAreaLayoutGuide: UILayoutGuide`

The layout guide representing the portion of your view that is unobscured by bars and other content.

`func safeAreaInsetsDidChange()`

Called when the safe area of the view changes.

`var insetsLayoutMarginsFromSafeArea: Bool`

A Boolean value indicating whether the view's layout margins are updated automatically to reflect the safe area.

Managing the View's Constraints

`var constraints: [NSLayoutConstraint]`

The constraints held by the view.

`func addConstraint(NSLayoutConstraint)`

Adds a constraint on the layout of the receiving view or its subviews.

`func addConstraints([NSLayoutConstraint])`

Adds multiple constraints on the layout of the receiving view or its subviews.

`func removeConstraint(NSLayoutConstraint)`

Removes the specified constraint from the view.

`func removeConstraints([NSLayoutConstraint])`
Removes the specified constraints from the view.

Working with Layout Guides

`func addLayoutGuide(UILayoutGuide)`
Adds the specified layout guide to the view.

`var layoutGuides: [UILayoutGuide]`
The array of layout guide objects owned by this view.

`var layoutMarginsGuide: UILayoutGuide`
A layout guide representing the view's margins.

`var readableContentGuide: UILayoutGuide`
A layout guide representing an area with a readable width within the view.

`func removeLayoutGuide(UILayoutGuide)`
Removes the specified layout guide from the view.

Measuring in Auto Layout

```
func systemLayoutSizeFitting(CGSize) -> CGSize
```

Returns the optimal size of the view based on its current constraints.

```
func systemLayoutSizeFitting(CGSize, withHorizontalFittingPriority: UILayoutPriority, verticalFittingPriority: UILayoutPriority) -> CGSize
```

Returns the optimal size of the view based on its constraints and the specified fitting priorities.

```
var intrinsicContentSize: CGSize
```

The natural size for the receiving view, considering only properties of the view itself.

```
func invalidateIntrinsicContentSize()
```

Invalidates the view's intrinsic content size.

```
func contentCompressionResistancePriority(for: NSLayoutConstraint.Axis) -> UILayoutPriority
```

Returns the priority with which a view resists being made smaller than its intrinsic size.

```
func setContentCompressionResistancePriority(UILayoutPriority, for: NSLayoutConstraint.Axis)
```

Sets the priority with which a view resists being made smaller than its intrinsic size.

```
func contentHuggingPriority(for: NSLayoutConstraint.Axis) -> UILayoutPriority
```

Returns the priority with which a view resists being made larger than its intrinsic size.

```
func setContentHuggingPriority(UILayoutPriority, for: NSLayoutConstraint.Axis)
```

Sets the priority with which a view resists being made larger than its intrinsic size.

Creating Constraints Using Layout Anchors

```
func alignmentRect(forFrame: CGRect) -> CGRect
```
Returns the view's alignment rectangle for a given frame.

```
func frame(forAlignmentRect: CGRect) -> CGRect
```
Returns the view's frame for a given alignment rectangle.

```
var alignmentRectInsets: UIEdgeInsets
```
The insets from the view's frame that define its alignment rectangle.

~~`func forBaselineLayout() -> UIView`~~
Returns a view used to satisfy baseline constraints.
Deprecated

```
var forFirstBaselineLayout: UIView
```
Returns a view used to satisfy first baseline constraints.

```
var forLastBaselineLayout: UIView
```
Returns a view used to satisfy last baseline constraints.

Creating Constraints Using Layout Anchors

Attach Auto Layout constraints to one of the view's anchors.

```
var bottomAnchor: NSLayoutYAxisAnchor
```
A layout anchor representing the bottom edge of the view's frame.

```
var centerXAnchor: NSLayoutXAxisAnchor
```
A layout anchor representing the horizontal center of the view's frame.

`var centerYAnchor: NSLayoutYAxisAnchor`
A layout anchor representing the vertical center of the view's frame.

`var firstBaselineAnchor: NSLayoutYAxisAnchor`
A layout anchor representing the baseline for the topmost line of text in the view.

`var heightAnchor: NSLayoutDimension`
A layout anchor representing the height of the view's frame.

`var lastBaselineAnchor: NSLayoutYAxisAnchor`
A layout anchor representing the baseline for the bottommost line of text in the view.

`var leadingAnchor: NSLayoutXAxisAnchor`
A layout anchor representing the leading edge of the view's frame.

`var leftAnchor: NSLayoutXAxisAnchor`
A layout anchor representing the left edge of the view's frame.

`var rightAnchor: NSLayoutXAxisAnchor`
A layout anchor representing the right edge of the view's frame.

`var topAnchor: NSLayoutYAxisAnchor`
A layout anchor representing the top edge of the view's frame.

`var trailingAnchor: NSLayoutXAxisAnchor`
A layout anchor representing the trailing edge of the view's frame.

`var widthAnchor: NSLayoutDimension`
A layout anchor representing the width of the view's frame.

Configuring Content Margins

`var directionalLayoutMargins: NSDirectionalEdgeInsets`

The default spacing to use when laying out content in a view, taking into account the current language direction.

`var layoutMargins: UIEdgeInsets`

The default spacing to use when laying out content in the view.

`var preservesSuperviewLayoutMargins: Bool`

A Boolean value indicating whether the current view also respects the margins of its superview.

`func layoutMarginsDidChange()`

Notifies the view that the layout margins changed.
