



USER MANUAL

PALLET MERGE ENHANCEMENT

User Manual

Inventory Supervisor & Documentation Staff Guide

PREPARED FOR



Vifel Ice Plant & Cold Storage, Inc.

05 August 2026

Prepared by **Elyon Solutions International Inc.**

Contents

- How to use this manual
- 2** Client Configuration
 - 2.1 Open the client
 - 2.2 Open the VIFEL Configuration tab
 - 2.3 Turn on merging
 - 2.4 Choose how the client merges
 - 2.5 Document options (Lot No. / Batch # / Prodcodes)
 - 2.6 Save
- 3** Encoding Lot No. & Batch # (→ Prodcodes)
 - 3.1 Before you start
 - 3.2 Open a new Receiving Report
 - 3.3 Enter Lot No. & Batch #
 - 3.4 Validate - the Prodcodes are generated
- 4** Receiving & Merge
 - 4.1 Start a merge
 - 4.2 Merge Type 1 - Fixed Merge Pallet
 - 4.3 Merge Type 2 - Multiple Special Pallets
 - 4.4 Un-merge
- 5** Withdrawal & Pallet Counting
 - 5.1 How pallets are counted
 - 5.2 Lot No., Batch # & Prodcodes on the withdrawal

How to use this manual

This manual walks you through the Merge Pallet feature one screen at a time. It is written for the Inventory Supervisor and Documentation Staff - each task is broken into short, numbered steps with a matching screenshot, so you can follow along directly on your own screen.

READING THE SCREENSHOTS

- A red box shows exactly where to look or click on the screen.
- A blue numbered circle matches the numbered Step in the text beside it.
- Screens are cropped to the part that matters - your screen shows more around it.
- Labels in bold (e.g. Can Merge Pallets) are the exact words you will see in the system.

WHO DOES WHAT

- Client configuration (Chapter 2) is set up by the Inventory Supervisor.
- Encoding receipts (RR) and withdrawals (WR) is done by Documentation Staff.

Chapter 2 below - Client Configuration - is the one-time setup that turns merging on for a client. The chapters that follow cover encoding Lot No. & Batch #, merging during receiving, withdrawal, and reporting.

Chapter 2 · Client Configuration

Merging is set up per client. Nothing changes for a client until it is switched on here - so this is where every merge client begins. It is done once, and only revisited if the client's setup changes.

WHO DOES THIS · BEFORE YOU START

- Responsible role: the Inventory Supervisor sets up client configuration. Documentation Staff who need a client configured should ask the Inventory Supervisor.
- It is done once per client (and again only if the client's setup changes).
- Have the client's merge details ready: whether they use one fixed pallet or several special pallet types, and whether they track Lot No. / Batch #.

2.1 Open the client

Step 1 · Open Contacts

From the Odoo home screen, click Contacts.




Figure 2.1 - The Contacts app on the Odoo home screen.

Step 2 · Open the client you want to set up

Search for the client by name, then click their card to open it.





Figure 2.2 - Search for the client in the Contacts list.

2.2 Open the VIFEL Configuration tab

Step 3 · Go to VIFEL Configuration

On the client form, scroll down to the row of tabs and click VIFEL Configuration. All merge settings live on this tab.




Contacts & Addresses	Sales & Purchase	Internal Notes	VIFEL Configuration
PALLET MERGING Can Merge Pallets ? ☐ DOCUMENTS Show Lot No. ? ☒ Show Batch # / ☒ Prodcod ? ☒			

Figure 2.3 - The VIFEL Configuration tab on the client form.

2.3 Turn on merging

Step 4 · Tick Can Merge Pallets

Under PALLET MERGING, tick Can Merge Pallets. A new section, HOW THIS CLIENT MERGES, appears below - that is where you choose the merge style.



PALLET MERGING	DOCUMENTS
Can Merge Pallets ? ☒	Show Lot No. ? ☒
Show Batch # / ☒	Prodcod ? ☒
HOW THIS CLIENT MERGES	
Multiple Pallet Support ? ☐	
Off — every merge is offered the same one pallet, named below.	
Fixed Merge Pallet ?	
Fixed Merge PSI ?	

Figure 2.4 - Turning on Can Merge Pallets reveals the merge options.

2.4 Choose how the client merges

There are two merge styles. The Multiple Pallet Support switch decides which one this client uses - follow Option A or Option B, not both.


Option A - Fixed Merge Pallet (switch OFF)

Leave Multiple Pallet Support unticked. Every merge for this client goes onto one dedicated pallet.

Step 5 · Leave Multiple Pallet Support OFF

Step 6 · Enter the Fixed Merge Pallet and Fixed Merge PSI

Type the client's dedicated pallet number in Fixed Merge Pallet, and its series in Fixed Merge PSI.



Multiple Pallet Support ? ☐	
Off — every merge is offered the same one pallet, named below.	
Fixed Merge Pallet ?	00001 B
Fixed Merge PSI ?	WM-32423

Figure 2.5 - Fixed mode: one dedicated pallet and its PSI.

Option B - Multiple Special Pallets (switch ON)

Tick Multiple Pallet Support. The client's special pallet types appear in the Pallet Types table, each with its own prefix and running number (for example MDGM, SDMG, TDMG, BOC).

Step 5 · Tick Multiple Pallet Support

Step 6 · Review the Pallet Types

The standard types are created automatically. You normally do not need to change them.

HOW THIS CLIENT MERGES

Multiple Pallet Support ☒ **5**

On — merges are offered the client's special pallets, listed below.

Include Regular Pallets ☐

6

Description	Prefix	Next Number	Next Series	
Mildly Damaged	MDGM	1	MDGM-000001	
Semi Damaged	SDMG	1	SDMG-000001	
Totally Damaged	TDMG	1	TDMG-000001	
Client Static PSI	BOC	1	BOC-000001	

Figure 2.6 - Multiple mode: the client's special pallet types.

Step 7 · Optional - Include Regular Pallets

Tick Include Regular Pallets only if this client may also merge onto ordinary stock pallets, not just their special ones.

HOW THIS CLIENT MERGES

Multiple Pallet Support ☒

On — merges are offered the client's special pallets, listed below.

Include Regular Pallets ☒ **7**

PALLET TYPES

Figure 2.7 - Include Regular Pallets (optional).

2.5 Document options (Lot No. / Batch # / Prodcod)

Step 8 · Set the DOCUMENTS options

Under DOCUMENTS, tick Show Lot No. and Show Batch # / Prodcod if this client tracks them. These control the fields you will encode during receiving (covered in Chapter 3).




Figure 2.8 - Document tracking options for the client.

2.6 Save

Step 9 · Save the client

Click the save (cloud) icon at the top of the form. The client is now ready to use merging.



Figure 2.9 - Save the client with the cloud icon.

WHAT'S NEXT


- Chapter 3 - Encoding Lot No. & Batch # (→ Prodcodes).

Chapter 3 · Encoding Lot No. & Batch # (→ Prodcod)

Some clients track a Lot No. and a Batch # on every pallet they receive. You type these while encoding the Receiving Report; when the receipt is validated, the system automatically builds a Prodcod from them and keeps it with the stock. This chapter shows the whole flow.

WHO DOES THIS · BEFORE YOU START

- Responsible role: encoding receipts (RR) and withdrawals (WR) is done by Documentation Staff. Client configuration (Chapter 2) is the Inventory Supervisor's task.
- The client must have Show Lot No. and Show Batch # / Prodcod switched on - set once by the Inventory Supervisor in the client's VIFEL Configuration (Chapter 2).



Reminder - the client's Lot No. / Batch # options, set in Chapter 2.

3.1 Before you start

Make sure the receipt is for a client that has Lot No. / Batch # enabled. If it is not, ask your Inventory Supervisor to switch it on (see Chapter 2).

3.2 Open a new Receiving Report

Step 1 · Open Inventory

From the Odoo home screen, click Inventory.




Figure 3.1 - The Inventory app.

Step 2 · Open RECEIVING

On the Inventory Overview, click the RECEIVING operation type.



Figure 3.2 - The RECEIVING operations card.

Step 3 · Create a new receipt

Click New to start a new Receiving Report.




Figure 3.3 - Start a new Receiving Report.

Step 4 · Select the client and encode as usual

Choose the client in the Customer field, then fill in the Receiving Report as you normally would. Follow the on-screen “Steps to Begin” note - set the Destination Location and remember to save (Alt + S).




Figure 3.4 - Select the client, then encode the receipt as usual.


3.3 Enter Lot No. & Batch

You can enter Lot No. and Batch # in either of two places - use whichever you prefer. Both write to the same lines.

Option A - in the Pallet Breakdown

Step 5 · Type Lot No. and Batch # on each line

In the Detailed Operations (Pallet Breakdown) grid, fill the Lot No. and Batch # columns for each pallet line.




#	Product	Use as Te...	Return C...	Special H...	SH Reas...	Vifel Locati...	Merged	Locati...	Pallet Seri...	Pallet...	Container...	Lot No.	Batch #	Prod. Da...	Exp. Da...	Quant...	Quantity ...
1	30CTNS / 2...		0			17AR05L5.1		Merge Pallet	M/EX/17...	WM-000032	C-23423	1	25	01/01/2026	01/01/20...	25.00	BXS
2	30CTNS / 2...		0			17AR05L5.2		Merge Pallet	M/EX/17...	WM-000033	C-23423	2	25	01/01/2026	01/01/20...	25.00	BXS
3	30CTNS / 2...		0			17AR05L6.1		Merge Pallet	M/EX/17...	WM-000034	C-23423	3	25	01/01/2026	01/01/20...	25.00	BXS
4	30CTNS / 2...		0			17AR05L6.2		Merge Pallet	M/EX/17...	WM-000035	C-23423	4	25	01/01/2026	01/01/20...	25.00	BXS
5	30CTNS / 2...		0			17AR05L7.2		Merge Pallet	M/EX/17...	WM-000036	C-23423	5	25	01/01/2026	01/01/20...	25.00	BXS
																125.00	

Figure 3.5 - Lot No. and Batch # columns in the Pallet Breakdown.

Option B - in the Magic Wizard

Step 6 · Enter them in the Magic Wizard

Click Magic Wizard to open Fast Encode RR Lines, then fill the Lot No. and Batch # columns there. Click Confirm when done.




Is a Pallet...	# Products	Original P...	Needs N...	Original L...	Pallet Seri...	RR Pallet...	Location	Container...	Lot N...	Batch...	Prod. Date	Exp. Date	Quantity	Qty UO...	Weight (K...	Pa
	1	30CTNS / 2...	WM-000032		M/EX/17/A...	WM-000032	M/EX/17/A...	Merge C-23423	1	25	01/01/2026	01/01/2027	25.00	BXS	250.000	0
	2	30CTNS / 2...	WM-000033		M/EX/17/A...	WM-000033	M/EX/17/A...	Merge C-23423	2	25	01/01/2026	01/01/2027	25.00	BXS	250.000	0
	3	30CTNS / 2...	WM-000034		M/EX/17/A...	WM-000034	M/EX/17/A...	Merge C-23423	3	25	01/01/2026	01/01/2027	25.00	BXS	250.000	0
	4	30CTNS / 2...	WM-000035		M/EX/17/A...	WM-000035	M/EX/17/A...	Merge C-23423	4	25	01/01/2026	01/01/2027	25.00	BXS	250.000	0
	5	30CTNS / 2...	WM-000036		M/EX/17/A...	WM-000036	M/EX/17/A...	Merge C-23423	5	25	01/01/2026	01/01/2027	25.00	BXS	250.000	0
															1,250.00	

Figure 3.6 - Lot No. and Batch # in the Magic Wizard.

3.4 Validate - the Prodcod is generated

Step 7 · Validate the receipt

Finish and validate the Receiving Report. Once it reaches Done, the stock is created.



New All Transfers M/RR/05320

Create Next Operation Unlocked Void Transfer Tally Sheet Pallet Tag Forms Receiving R. Summary Receiving R. Per Pallet

☆ M/RR/05320 Customer: Wonder Meats


Packages Traceability Pallet Breakdown Location Related Stocks Pallet Audit 10

7 Draft Ready Done

Figure 3.7 - The receipt validated (Done); the stock is created.

Step 8 · Open Location Related Stocks to see the Prodcod

Click Location Related Stocks on the receipt. Each stored pallet now carries its Prodcodex, built automatically from the Expiration Date and the Batch #, followed by a fixed letter M - for example 01JAN2027 + 25 + M.



	Vifel Locati...	Location	Product	Return Cou...	Pallet...	Pallet Series...	Lot N...	Batch...	Prodcodex	Container...	Production ...	Expiration D...	Total
☐	17AR05L5.1	M/EX/17/A/R...	30CTNS / 243...	0	01901 B	WM-000032	1	25	01JAN202725...	C-23423	01/01/2026	01/01/2027	
☐	17AR05L5.2	M/EX/17/A/R...	30CTNS / 243...	0	0194 B	WM-000033	2	25	01JAN202725...	C-23423	01/01/2026	01/01/2027	
☐	17AR05L6.1	M/EX/17/A/R...	30CTNS / 243...	0	020 BP	WM-000034	3	25	01JAN202725...	C-23423	01/01/2026	01/01/2027	
☐	17AR05L6.2	M/EX/17/A/R...	30CTNS / 243...	0	02091 B	WM-000035	4	25	01JAN202725...	C-23423	01/01/2026	01/01/2027	
☐	17AR05L7.2	M/EX/17/A/R...	30CTNS / 243...	0	021 B	WM-000036	5	25	01JAN202725...	C-23423	01/01/2026	01/01/2027	

Figure 3.8 - The Prodcodex stored on each pallet (Location Related Stocks).

The Prodcodex stays with the stock and is also shown, read-only, on the withdrawal's Pallet Breakdown.

Step 9 · See the Prodcodex on a withdrawal

Inventory

Overview

Operations

Products

Reporting

Locations

Configuration

Quants

Menu

Stock Quants / MWR/08432

Q Search...

1-4 / 4

☐	#	Product	Return C...	Special H...	SH Reason	Pallet...	Pick From	Pallet Ser...	Container...	Lot N...	Prodcodex	Prod. Date	Exp. Date	Original ...	Quantity ...	Actual Qu...	Quantity ...	Original ...	Weight (K...	Actual KG	Original ...	Packs	Actual Pa...	Packs UO...
☐	1	30CTNS / 2...	0	☐		0194 B	M/EX/17/A...	WM-000033	C-23423	2	01JAN2027...	1/01/2026	01/01/20...	25.00	25.00	25.00	BXS	250.00	250.000	250.000	0.00	0.00	0.00	
☐	2	30CTNS / 2...	0	☐		020 BP	M/EX/17/A...	WM-000034	C-23423	3	01JAN2027...	1/01/2026	01/01/20...	25.00	25.00	25.00	BXS	250.00	250.000	250.000	0.00	0.00	0.00	
☐	3	30CTNS / 2...	0	☐		02091 B	M/EX/17/A...	WM-000035	C-23423	4	01JAN2027...	1/01/2026	01/01/20...	25.00	25.00	25.00	BXS	250.00	250.000	250.000	0.00	0.00	0.00	
☐	4	30CTNS / 2...	0	☐		021 B	M/EX/17/A...	WM-000036	C-23423	5	01JAN2027...	1/01/2026	01/01/20...	25.00	25.00	25.00	BXS	250.00	250.000	250.000	0.00	0.00	0.00	
														100.00	100.00	100.00		1,000.00	1,000.00	1,000.000	0.00	0.00	0.00	

9

Figure 3.9 - The Prodcodex (read-only) on a later withdrawal.

WHAT'S NEXT

- Chapter 4 - Receiving & Merge (Fixed and Multiple).

Chapter 4 · Receiving & Merge

During receiving you can merge a pallet line onto another pallet, so several products or batches share one physical pallet. How the merge behaves depends on the client's setup (Chapter 2): a Fixed client uses one dedicated pallet; a Multiple client has several special pallets. Either way the merge starts the same, and any merge can be reversed with Un-merge.

WHO DOES THIS · BEFORE YOU START

- Responsible role: Documentation Staff merge pallets while encoding the receipt.
- The client must have Can Merge Pallets switched on (set by the Inventory Supervisor - Chapter 2).
- Merging onto a pallet that already holds stock does not add to the pallet count (+0). The first stock on an empty pallet, or a brand-new special pallet, counts as one received pallet (+1).

4.1 Start a merge

The merge starts the same way for every client. On the receipt's Pallet Breakdown, find the line you want to merge and click Merge Pallet.

Step 1 · Click Merge Pallet on the line

☐	^	#	Product	Use as Te...	Return C...	Special H...	SH Reas...	Vifel Locati...	Merged		Location	Pallet Se
☐		1	40CTNS / 3...	☐	0	☐		17Aisle 2	☐		17/Aisle 2	WM-000
☐		2	40CTNS / 3...	☐	0	☐		17Aisle 2	☐		M/EX/17/Aisle 2	WM-000
☐		3	40CTNS / 3...	☐	0	☐		17Aisle 2	☐		M/EX/17/Aisle 2	WM-000
☐		4	40CTNS / 3...	☐	0	☐		17Aisle 2	☐		M/EX/17/Aisle 2	WM-000

Figure 4.1 - The Merge Pallet button on a receipt line.

Step 2 · Or start it from the Magic Wizard

You can also open the Magic Wizard and click Merge on the line - it opens the same dialog.

Fast Encode RR Lines												
☒ Confirm		Search...										
☐	Is a Pallet...	#	Products	Original P...	Needs N...	Original L...	Pallet Seri...	RR Pallet...	Location		Container...	Lot N...
☐	☐	1	40CTNS / 3...	WM-000037	☐	M/EX/17/Ai...	WM-000037		M/EX/17/Aisle 2			
☐	☐	2	40CTNS / 3...	WM-000038	☐	M/EX/17/Ai...	WM-000038		M/EX/17/Aisle 2			
☐	☐	3	40CTNS / 3...	WM-000039	☐	M/EX/17/Ai...	WM-000039		M/EX/17/Aisle 2			
☐	☐	4	40CTNS / 3...	WM-000040	☐	M/EX/17/Ai...	WM-000040		M/EX/17/Aisle 2			
☐	☐	5	40CTNS / 3...	WM-000041	☐	M/EX/17/Ai...	WM-000041		M/EX/17/Aisle 2			
☐	☐	6	40CTNS / 3...	WM-000042	☐	M/EX/17/Ai...	WM-000042		M/EX/17/Aisle 2			

Figure 4.2 - Starting a merge from the Magic Wizard.

4.2 Merge Type 1 - Fixed Merge Pallet

For a Fixed client, the dialog already has the client's one dedicated pallet set to Merge Here - you just confirm.

Step 3 · Review and Confirm

Check that Merge Here is on for the fixed pallet, then click Confirm. If the pallet is still empty, this first line counts as one received pallet; later lines merging onto it (once it holds stock) do not.

Figure 4.3 - Fixed mode: the dedicated pallet is pre-selected.

Step 4 · The line is now merged

The line adopts the fixed pallet's series and now shows Un-merge.

#	Product	Use as Te...	Return C...	Special H...	SH Reas...	Vifel Locati...	Merged	Location	Pallet Seri...	Pallet...	Container...	Lot N
1	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000037	C-34523	26
2	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000038	C-34523	26
3	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000039	C-34523	26
4	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000040	C-34523	26
5	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000041	C-34523	26
6	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000042	C-34523	26
7	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000043	C-34523	26
8	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000044	C-34523	26
9	40CTNS / 3...	☐	0	☐		17Aisle 2	☐	Merge Pallet	M/EX/17/Aisle 2	WM-000045	C-34523	26
10	40CTNS / 3...	☐	0	☐		17Aisle 2	☒	Un-merge	M/EX/17/Aisle 2	WM-32423 00001 B	C-34523	26

Figure 4.4 - The merged line on the fixed pallet (WM-32423 / 00001 B).

4.3 Merge Type 2 - Multiple Special Pallets

For a Multiple client, click Merge Pallet on the line the same way - but the dialog now offers two choices: merge onto a pallet already stocked, or start a new special pallet.

Figure 4.5 - A Multiple client's receipt; start the same way with Merge Pallet.

Option A - Merge onto a pallet already stocked

Step 5 · Pick the pallet to merge onto

Choose Merge onto a pallet already stocked. The client's special pallets currently in storage are listed. Turn on Merge Here for the one you want - its current contents appear under On the selected pallet - then click Confirm.

# Line #	Product	Currently PSI On	Quantity	Quantity UOM	Weight (KG)
10	BEEF TENDON ACHILLES (DAWN MEAT) (DAWN MEAT)	CON-003058	35.00	BXS	759.00

Merge onto a pallet already stocked (5)

☒ Merge Here ☐ Start a NEW special pallet

Merge Here	Pallet Series	Where	Product	Location	Quantity	Weight (KG)
☒	MDMG-000001	In storage	094-8 HLISO SHRIMP 31/40 (VANNAME)	M/A/1/A/R01/L1/P1	50.00	1,500.000
☐	SDMG-000001	In storage	094-8 HLISO SHRIMP 31/40 (VANNAME)	M/M/1/Aisle 2	50.00	1,550.000
☐	TDMG-000001	In storage	APRUB CHICKEN SIOMAI 305 (500G), 094-8 HLISO SHRIMP 31/40 (VANNAME)	M/M/1/Aisle 1	75.00	1,900.000
☐	TDMG-000002	In storage	094-8 HLISO SHRIMP 31/40 (VANNAME), APRUB CHICKEN SIOMAI 305 (500G)	M/M/1/Aisle 1	50.00	1,550.000
☐	TDMG-000003	In storage	APRUB CHICKEN SIOMAI 305 (500G)	M/M/1/Aisle 1	25.00	750.000
☐	TDMG-000004	In storage	APRUB CHICKEN SIOMAI 305 (500G)	M/M/1/Aisle 1	50.00	1,550.000

ON THE SELECTED PALLET

Receiving Record (RR)	Product	Pallet Series	Location	Quantity	Quantity UOM	Weight (KG)
M/RR/05316	094-8 HLISO SHRIMP 31/40 (VANNAME)	MDMG-000001	M/A/1/A/R01/L1/P1	25.00	CRATES	750.000
M/RR/05316	094-8 HLISO SHRIMP 31/40 (VANNAME)	MDMG-000001	M/A/1/A/R01/L1/P1	25.00	CRATES	750.000

Figure 4.6 - Choosing an existing special pallet to merge onto.

Option B - Start a NEW special pallet

Step 6 · Fill the three details

Choose Start a NEW special pallet, then fill all three: PSI Type, New Empty Pallet, and New Location. Click Confirm - the pallet is created and assigned to the line. A new special pallet counts as one received pallet (+1).

Start a NEW special pallet

NEW SPECIAL PALLET — COUNTS AS A RECEIVED PALLET (+1)

PSI Type ? Client Static PSI

New Empty Pallet ? 02267 B

New Location ? M/A/1/A/R02/L5/P2

Confirm Cancel

M/A/1/A/R02/L5/P2
M/A/1/A/R02/L6/P1
M/A/1/A/R02/L6/P2
M/A/1/A/R02/L7/P1

Figure 4.7 - Starting a new special pallet.

Step 7 · Confirmation

A notification confirms the new pallet, and the line now shows Un-merge on it.

Pallet merge

New special pallet 02267 B started (BOC-000001) with 1 line(s).


#	Product	Use as Te...	Return C...	Special H...	SH Reas...	Vifel Locat...	Merged	Location	Pallet Ser...	Pallet...	Container...	Lot N...	Batch...	Prod. Da...	Exp. Date	Quantity	Weight (KG)
1	BEEF TEND...		0			1AR02L1.1	☒ Merge Pallet	M/A/1/A/R...	CON-003049		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
2	BEEF TEND...		0			1AR02L1.2	☒ Merge Pallet	M/A/1/A/R...	CON-003050		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
3	BEEF TEND...		0			1AR02L1.1	☒ Merge Pallet	M/A/1/A/R...	CON-003051		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
4	BEEF TEND...		0			1AR02L2.2	☒ Merge Pallet	M/A/1/A/R...	CON-003052		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
5	BEEF TEND...		0			1AR02L3.1	☒ Merge Pallet	M/A/1/A/R...	CON-003053		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
6	BEEF TEND...		0			1AR02L3.2	☒ Merge Pallet	M/A/1/A/R...	CON-003054		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
7	BEEF TEND...		0			1AR02L4.1	☒ Merge Pallet	M/A/1/A/R...	CON-003055		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
8	BEEF TEND...		0			1AR02L4.2	☒ Merge Pallet	M/A/1/A/R...	CON-003056		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
9	BEEF TEND...		0			1AR02L5.1	☒ Merge Pallet	M/A/1/A/R...	CON-003057		C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
10	BEEF TEND...		0			1AR02L5.2	☒ Un-merge	M/A/1/A/R...	BOC-000001	02267 B	C-23453	10	25	01/01/2026	01/01/20...	35.00	759.000
																350.00	7,590.00

Figure 4.8 - The new special pallet created and assigned to the line.

4.4 Un-merge

Any merged line can be reversed. Click Un-merge on the line - its original Pallet Series comes back, and the pallet count self-corrects.

Step 8 · Click Un-merge



02LS.1	☐	 Merge Pallet	M/A/1/A/R...	CON-003057	C-23453
02LS.2	☒	 Un-merge	M/A/1/A/R...	BOC-000001 02267 B	C-23453

Figure 4.9 - Un-merge returns the line's original pallet.

WHAT'S NEXT

- Chapter 5 - Withdrawal & Pallet Counting.

Chapter 5 · Withdrawal & Pallet Counting

Withdrawing merged stock is done exactly like any other withdrawal - the merge feature adds no extra steps here. What is worth knowing is how a merge pallet is counted on your printouts, and that the Lot No., Batch #, and Prodcod stay visible when you withdraw.

WHO DOES THIS

- Responsible role: Documentation Staff encode withdrawals (WR) - the same as any withdrawal.

5.1 How pallets are counted

One physical pallet is always counted once. This table shows how each scenario is counted on the receiving and withdrawal printouts.

Scenario	Counts as
Receiving - merge onto a pallet that already holds stock	+0 (no new pallet)
Receiving - first stock on an empty pallet, or a new special pallet	+1
Withdrawal - partial (stock still left on the pallet)	-0 (pallet stays)
Withdrawal - full (pallet emptied)	-1

If a shared pallet is split across several trucks, it is counted on the withdrawal that empties it - not on the first truck that draws from it.

5.2 Lot No., Batch # & Prodcod on the withdrawal

When you withdraw, the Lot No. and the stored Prodcod (which already includes the Batch #) are shown, read-only, on the withdrawal's Pallet Breakdown, so the same identifiers follow the stock all the way out.

#	Product	Return C.	Special H.	SH Reason	Pallet	Pick From	Pallet Ser.	Container	Lot No.	Prodcod	Mod. Date	Exp. Date	Original Quantity	Actual Quantity	Weight (K)	Actual KG	Original Packs	Actual Pa.	Packs UO
1	30CTNS / 2...	0			0194 B	M/EX/17/A...	WM-000033	C-23423	2	01JAN2027...	01/01/2026	01/01/20...	25.00	25.00	250.00	250.000	0.00	0.00	0.00
2	30CTNS / 2...	0			0200 BP	M/EX/17/A...	WM-000034	C-23423	3	01JAN2027...	01/01/2026	01/01/20...	25.00	25.00	250.00	250.000	0.00	0.00	0.00
3	30CTNS / 2...	0			02091 B	M/EX/17/A...	WM-000035	C-23423	4	01JAN2027...	01/01/2026	01/01/20...	25.00	25.00	250.00	250.000	0.00	0.00	0.00
4	30CTNS / 2...	0			021 B	M/EX/17/A...	WM-000036	C-23423	5	01JAN2027...	01/01/2026	01/01/20...	25.00	25.00	250.00	250.000	0.00	0.00	0.00
													100.00	100.00	1,000.00	1,000.000	0.00	0.00	0.00

Figure 5.1 - Lot No. and Prodcod shown (read-only) on a withdrawal.

THAT'S THE WHOLE FLOW

- Client Configuration → Lot / Batch encoding → Merge on receiving → Withdrawal & counting.
- One physical pallet, counted once - from receiving all the way to withdrawal.