

```
msf > use auxiliary/scanner/telnet/telnet_version

Matching Modules

#  Name                                     Disclosure Date  Rank  Check  Description
-  -
0  auxiliary/scanner/telnet/telnet_version  .              normal No     Telnet Service Banner Detection

Interact with a module by name or index. For example info 0, use 0 or use auxiliary/scanner/telnet/telnet_version

[*] Using auxiliary/scanner/telnet/telnet_version
msf auxiliary(scanner/telnet/telnet_version) > 
```

```
msf auxiliary(scanner/telnet/telnet_version) > show options

Module options (auxiliary/scanner/telnet/telnet_version):

Name  HP int Current Setting  Required  Description
-  -  -
PASSWORD  Password for the specified username
RHOSTS  The target host(s), see https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html
RPORT  23  The target port (TCP)
THREADS  1  The number of concurrent threads (max one per host)
TIMEOUT  30  Timeout for the Telnet probe
USERNAME  msfadmin  The username to authenticate as

View the full module info with the info, or info -d command.

msf auxiliary(scanner/telnet/telnet_version) > set RHOST 192.168.1.150
RHOST => 192.168.1.150
```

```
msf auxiliary(scanner/telnet/telnet_version) > exploit
[*] 192.168.1.150:23 - 192.168.1.150:23 TELNET
dev[at]metasploit.com\x0a\x0aWarning: Never expose this VM to an untrusted network!\x0a\x0aContact: msfdev[at]metasploit.com
[*] 192.168.1.150:23 - Scanned 1 of 1 hosts (100% complete)
[*] Auxiliary module execution completed
```

```
msf auxiliary(scanner/telnet/telnet_version) > telnet 192.168.1.150
[*] exec: telnet 192.168.1.150

Trying 192.168.1.150 ...
Connected to 192.168.1.150.
Escape character is '^]'.

Warning: Never expose this VM to an untrusted network!
Contact: msfdev[at]metasploit.com

Login with msfadmin/msfadmin to get started

metasploitable login: 
```

```
metasploitable login: msfadmin
Password:
Last login: Thu Jul 30 12:16:38 EDT 2026 on tty1
Linux metasploitable 2.6.24-16-server #1 SMP Thu Apr 10 13:58:00 UTC 2008 i686

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by applicable law.

To access official Ubuntu documentation, please visit:
http://help.ubuntu.com/
No mail.

msfadmin@metasploitable:~$ ifconfig
eth0      Link encap:Ethernet  HWaddr 08:00:27:7c:96:72
          inet addr:192.168.1.150  Bcast:192.168.1.255  Mask:255.255.255.0
          inet6 addr: fe80::a00:27ff:fe7c:9672/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:1823804 errors:0 dropped:0 overruns:0 frame:0
          TX packets:4241 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:2096857784 (1.9 GB)  TX bytes:1616793 (1.5 MB)
          Base address:0xd020 Memory:f0200000-f0220000

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:1442 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1442 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:661109 (645.6 KB)  TX bytes:661109 (645.6 KB)

msfadmin@metasploitable:~$ sudo ifconfig eth0 192.168.1.151 netmask 255.255.255.0 up
[sudo] password for msfadmin:
```

