[MP2] Failed to connect to QEMU

3 3

陳靖塘 (CHEN, JING-TANG)

All Sections

I've implemented the four API functions and am currently testing them. However, when I run `./mp2.sh test slab`, I encounter the following error message. How can I resolve this issue?

```
== Test Slab check (Max [3(+5): slab structure (with bonus)] + [2: max objects]) (10%) ==
Failed to connect to QEMU; output:
user/usys.S: Assembler messages:
user/usys.S:115: Error: illegal operands `li a7,SYS_printfslab'
make: *** [Makefile:110: user/usys.o] Error 1

Failed to shutdown QEMU.  You might need to 'killall qemu' or
'killall qemu.real'.
```

Search entries or author | Unread | Subscribe

Reply

(https:/

楊子慶 (YANG, TZU-CHING) (https://cool.ntu.edu.tw/courses/46296/users/229158)

Mar 26, 2025

Hello student,

Thank you for your question.
This is because you have not yet implemented the `sys_printfslab` system call. Please implement it first and then proceed with debugging.
If you have more questions, feel free to ask, or come visit during TA hours. Thank you.

Tzu-Ching

(http

陳靖塘 (CHEN, JING-TANG) (https://cool.ntu.edu.tw/courses/46296/users/143633)

Mar 26, 2025

Thanks for the advice! After implementing sys_printfslab, I received the error message: "Slab allocation is not working or in bad format, please check the implementation." for public/mp2-1, and the output is as follows.

```
[MP2] Slab size: 3
[SLAB] New kmem_cache (name: file_cache, object size: 504 bytes, at: 0x0000000087f59000, max objects per slab: 8,
hart 2 starting
hart 1 starting
[SLAB] Alloc request on cache file_cache
[SLAB] A new slab 0x0000000087f4e000 (file_cache) is allocated
[SLAB] Object 0x0000000087f4e018 in slab 0x0000000087f4e000 is allocated and initialized
init: starting sh
[SLAB] Alloc request on cache file_cache
[SLAB] Object 0x0000000087f4e210 in slab 0x0000000087f4e000 is allocated and initialized
$ echo Ok > ok
[SLAB] Alloc request on cache file_cache
[SLAB] Object 0x0000000087f4e408 in slab 0x0000000087f4e000 is allocated and initialized
$ qemu-system-riscv64: terminating on signal 15 from pid 24502 (make)
```

What could be causing this issue?

Edited by 陳靖塘 (CHEN, JING-TANG) (https://cool.ntu.edu.tw/courses/46296/users/143633) on Mar 26 at 8:21pm

(http

楊子慶 (YANG, TZU-CHING) (https://cool.ntu.edu.tw/courses/46296/users/229158)

Mar 26, 2025

Hello student,

There is an issue with your print format. Please double-check if there's a problem with the line `[SLAB] Object ....`.

For issues like this, since the error messages from the interpreter are already clear enough, it's not very suitable to ask about them. Students should handle these independently. This does not apply when the interpreter provides obscure or difficult-to-understand hints.

If you have more questions, please feel free to ask. Thank you.

Tzu-Ching

Reply