

2.4.9 Configure a Security Appliance

Lab Report

Time Spent: 06:58

Score: 3/3 (100%) **Pass**

Passing Score: 3/3 (100%)

TASK SUMMARY

Required Actions

- ✓ Configure DNS servers [Hide Details](#)
 - ✓ Configure the DNS1 server
 - ✓ Give the primary DNS server an IP address of 163.128.78.93
 - ✓ Name primary DNS server DNS1
 - ✓ Configure the DNS2 server
 - ✓ Give the secondary DNS server an IP address of 163.128.80.93
 - ✓ Name secondary DNS server DNS2
 - ✓ Configure the WAN settings [Hide Details](#)
 - ✓ Enable the WAN interface
 - ✓ Use static IPv4
 - ✓ Use IP address 65.86.24.136
 - ✓ Use a subnet mask of 255.0.0.0 (/8)
 - ✓ Add and configure a new gateway [Hide Details](#)
 - ✓ Gateway set as the default
 - ✓ Use a gateway name of WANGateway
 - ✓ Use the gateway IP address of 65.86.1.1
-

EXPLANATION

Complete this lab as follows:

1. Access the pfSense management console.
 - a. From the taskbar, select **Google Chrome**.
 - b. Maximize the window for better viewing.
 - c. In the address bar, type **198.28.56.22** and then press **Enter**.
 - d. Sign in using the following case-sensitive information:
 - Username: **admin**
 - Password: **pfsense**
 - e. Select **SIGN IN** or press **Enter**.
2. Configure the DNS Servers.
 - a. From the pfSense menu bar, select **System > General Setup**.
 - b. Under *DNS Server Settings*, configure the primary DNS server as follows:
 - Address: **163.128.78.93**

- Hostname: **DNS1**
- Gateway: **None**

c. Select **Add DNS Server** to add a secondary DNS server and then configure it as follows:

- Address: **163.128.80.93**
- Hostname: **DNS2**
- Gateway: **None**

d. Scroll to the bottom and select **Save**.

3. Configure the WAN settings.

- a. From pfSense menu bar, select **Interfaces > WAN**.
- b. Under General Configuration, select **Enable interface**.
- c. Use the *IPv4 Configuration Type* drop-down to select **Static IPv4**.
- d. Under Static IPv4 Configuration, in the *IPv4 Address* field, enter **65.86.24.136**.
- e. Use the IPv4 Address subnet drop-down to select **8**.
- f. Under Static IPv4 Configuration, select **Add a new gateway**.
- g. Configure the gateway settings as follows:
 - Default: Select **Default gateway**
 - Gateway name: Enter **WANGateway**
 - Gateway IPv4: **65.86.1.1**
- h. Select **Add**.
- i. Scroll to the bottom and select **Save**.
- j. Select **Apply Changes**.

Copyright © 2026 CompTIA, Inc. All rights reserved.