TMUX QUICK REFERENCE CARD

Frequently used TMUX commands – Version v1.0 June 2014

Prefix key is set to ⟨ctrl-b⟩ by default. You can change that behaviour to e.g. ⟨ctrl-a⟩ by adding the following commands to your ~/.tmux.conf:

```
:unbind C-b
:set -g prefix C-a
:bind C-a send-prefix
```

From Shell

```
create session
             tmux new -s session-name
kill session
             tmux kill-session -t session-name
attach session
             tmux a[ttach] -t session-name
         or  tmux a #
rename session
             tmux rename-session -t old-name new-
             name
list session
             tmux ls
```

Inside Tmux

⟨M⟩ denotes the meta key, usually bound to ⟨ALT⟩

Sessions

ˆb?	show all available keybinds
ˆbd ˆbs	detach / reattach to session
ˆbs	list all sessions

Copy Mode

`vim` like movements

h j k l	move left/down/up/right
ˆb[q	enter / exit copy mode
⟨space⟩ ← . . .	select / copy text under cursor
ˆb]	paste copied text to command line

Windows *or* Buffers

ˆbc ˆb, ...	create / rename window
ˆbf ˆbw	find / list windows
ˆb&	close current window
ˆbn ˆbp ˆbl . .	navigate next/prev/last window
ˆb*n*	switch to buffer 0...*n*

Open / Switch / Resize Panes

ˆbx *or* ˆd . . .	delete pane
ˆb!	push all other panes to next window
ˆbt ˆbq	show time / numeric values of panes
ˆb⟨⇔⇕⟩ *or* ˆbo	switch to (next) pane
ˆb#	show buffers
ˆb⟨M - ⇔⇕⟩ ˆbz	
	resize / full-screen pane
ˆb}	swap position with next pane
ˆb{ *or* ˆbˆo .	swap with previous pane

Split Panes

ˆb% ˆb"	split pane vertically / horizontally
ˆb⟨M-1⟩	vertical split, all panes same width
ˆb⟨M-2⟩	horizontal split, all panes same height
ˆb⟨M-3⟩	horizontal split, main pane on top, other panes on bottom, vertically split, all same width
ˆb⟨M-4⟩	vertical split, main pane left, other panes right, horizontally split, all same height
ˆb⟨M-5⟩	tile, new panes on bottom, same height before same width
ˆb⟨space⟩	toggle through all layouts