TMUX QUICK REFERENCE CARD

Prefix key is set to ⟨*ctrl-b*⟩ by default. You can change that behaviour to e.g. ⟨*ctrl-a*⟩ by adding the following commands to your ˜/.tmux.conf:

```
:unbind C-b
:set -g prefix C-a
:bind C-a send-prefix
```

From Shell

create session
    tmux new -s `session-name`
kill session
    tmux kill-session -t `session-name`
attach session
    tmux a[ttach] -t `session-name`
    or tmux a #
rename session
    tmux rename-session -t `old-name` `new-name`
list session
    tmux ls

Inside Tmux
⟨*M*⟩ denotes the meta key, usually bound to ⟨*ALT*⟩

Sessions

`ˆb?` . . . . show all available keybinds

`ˆbd` `ˆbs` . . . . . . detach / reattach to session

Copy Mode
`vim` like movements

`h j k l` . . . . . . move left/down/up/right

`ˆb[` `q` . . . . enter / exit copy mode

⟨*space*⟩ ↩ . . . select / copy text under cursor

`ˆb]` . . . . paste copied text to command line

Windows

`ˆbc` `ˆb,` . . . . . . create / rename window

`ˆbf` `ˆbw` . . . . . . find / list windows

`ˆbn` `ˆbp` `ˆbl` . . navigate next/prev/last window

Open / Switch / Resize Panes

`ˆbx` *or* `ˆd` . . . . delete pane

`ˆb!` . . . . close all other panes

`ˆbt` `ˆbq` . . . . . . show time / numeric values of panes

`ˆb⟨⇔⇕⟩` *or* `ˆbo` switch to (next) pane

`ˆb#` `ˆb`*n* . . . . . . show / switch to buffers 0...*n*

`ˆb⟨M - ⇔⇕⟩` `ˆbz`
        resize / full-screen pane

`ˆb}` . . . . swap position with next pane

`ˆb{` *or* `ˆbˆo` . . swap with previous pane

Split Panes *or* Buffers

`ˆb%` `ˆb"` . . . . . . split pane vertically / horizontally

`ˆb` ⟨*M-1*⟩ . . . . . vertical split, all panes same width

`ˆb` ⟨*M-2*⟩ . . . . . horizontal split, all panes same height

`ˆb` ⟨*M-3*⟩ . . . . . horizontal split, main pane on top, other panes on bottom, vertically split, all same width

`ˆb` ⟨*M-4*⟩ . . . . . vertical split, main pane left, other panes right, horizontally split, all same height

`ˆb` ⟨*M-5*⟩ . . . . . tile, new panes on bottom, same height before same width