Storege WMS User Manual

Detailed guide — v1.0

Overview

Storege WMS is a professional barcode + handheld warehouse management system for Saudi concrete plants, spare-parts workshops and vehicle consumables. 9 languages (Arabic/Urdu RTL), all prices in SAR, 15% tax.

Quick start

1) Sign in (admin@storege.app / Admin@12345). 2) Select a warehouse. 3) Add categories. 4) Add items (barcode/reorder). 5) Add locations (R01-C01). 6) Create PO. 7) Receive → putaway. 8) Create SO → allocate → pick → pack → ship.

Items

Manage SKU, EAN-13 barcode, cost/price, reorder point, strategic stock, max stock, reorder qty, lot/serial tracking, shelf life. CSV import/export. Search by barcode/code/name.

Locations

Multiple warehouses, zones, locations (PICK/DOCK/STAGING/SHIPPING/QUARANTINE), capacities, barcodes, rack/column (R01-C01).

Purchase orders

Create PO from supplier (items/qty/cost). ASN number + expected date. Partial/full receive. Cancel receive by reversing movements.

Receiving

Receive against PO, lot code/expiry/serials, choose location, putaway suggestion (consolidate/empty). Cross-dock.

Sales orders

Create SO from customer, FEFO auto-allocation, allocate stock, statuses OPEN/ALLOCATED/PICKING/PICKED/PACKED/SHIPPED. Priorities.

Picking

Pick tasks per allocation, picked quantities, staging location. Wave/Batch picking: combine multiple orders into one pick list (/wave-picking).

Pack & ship

Pack all lines, ship with carrier/tracking. Fields: issue reason (e.g. vehicle spare parts), vehicle/equipment (plate), delivered to. Print Issue Permit.

Transfers

Between warehouses: draft → in transit → receive. Lot/serial tracking.

Cycle counts

Count by location/zone/warehouse, enter counts, variances, approve to adjust stock. Blind counts + ABC.

Inventory

Real-time balance per item/location/lot/serial. Manual adjust with reason. Move. Stock ledger.

Totals

Aggregated view: units, SKUs, stock value, reserved/available, by warehouse/category, strategic alerts.

Page /totals.

Reports

Stock valuation, low stock, expiry, movement, dead stock, productivity, top items, ABC, count accuracy, purchase reconciliation, wave picking.

Purchase reconciliation

Compare invoiced quantities vs received vs on-hand (variance/status). Page /reconciliation.

Barcodes & labels

Camera/USB scanner, EAN-13/Code128 generator, label designer, A4/thermal print, ZPL export.

Handheld (/m)

Mobile UI for receive, putaway, pick, count. Offline (IndexedDB) + queue + idempotency (X-Op-Id).

Settings

Company data, logo upload (650KB), currency (SAR), tax 15%, labels, barcode prefix. Logo shown in sidebar and dashboard.

Users & roles

ADMIN/MANAGER/OPERATOR/VIEWER. Permissions, audit log.

Integrations

API keys, webhooks. ZATCA Phase 2 (QR+XML), Salla/Zid, ERP/EDI/TMS in roadmap.

Returns (RMA)

Customer/supplier returns. Statuses DRAFT→RECEIVED→COMPLETED/CANCELLED. Disposition RESTOCK/SCRAP/QUARANTINE. Page /returns.

Quality (QC)

PENDING/PASSED/FAILED on received lines. Page /quality.

Dock scheduling

Book appointments for trucks/docks, status updates. Page /docks.

Yard

Track yard spots (EMPTY/OCCUPIED) and trailers. Page /yard.

Labor

Track tasks (PICK/PUTAWAY/COUNT/RECEIVE) and time/qty. Page /labor.

Replenishment

Suggestions to move stock from reserve to pick face. Page /replenishment.

ZATCA

QR (TLV base64) + UBL 2.1 XML, button on invoice + download XML. Saudi compliance.

Languages

9 languages (Arabic/Urdu RTL). Change from top selector.

Detailed receiving

1) Create PO. 2) Open PO → receive. 3) Enter received qty + lot/expiry/serials. 4) Choose location (DOCK/STAGING). 5) Submit. 6) Putaway (auto-suggest). 7) System creates Stock + StockMovement (RECEIVE).

Detailed shipping

1) SO in ALLOCATED/PICKED. 2) Pack all lines. 3) Ship: carrier/tracking. 4) Fields: issue reason (e.g. vehicle spare parts), vehicle/equipment (plate), delivered to. 5) System deducts from shipping area and creates Shipment + Issue Permit (print).

Detailed cycle count

1) Create Cycle Count (warehouse/zone/location). 2) System generates lines (expectedQty). 3) Enter countedQty. 4) Approve → adjusts Stock and creates COUNT movements. 5) Count accuracy report.

Detailed move

1) Open Inventory → select item/location. 2) Click Move. 3) Enter qty + destination location. 4) System decrements source and increments destination.

Detailed adjust

1) Open Inventory → Adjust. 2) Enter signed qty (+/-) + reason. 3) System updates Stock and creates ADJUST movement. 4) Audit log.

Barcodes

USB/Bluetooth scanner (Keyboard Wedge): scan then Enter. Camera scanner: camera button (HTTPS/localhost). Generate EAN-13/Code128. Label designer. A4/thermal print. ZPL export.

Offline

PWA + IndexedDB. After first open (online), caches items/locations/POs/picking/counts. When offline, receive/putaway/pick/count are queued. On reconnect, auto-sync. X-Op-Id prevents duplicates.

Support

Developed by FimtoSoft — www.fimtosoft.com. Manual: /manual. PDF: /storege-manual-ar.pdf. APK: GitHub Releases.