Storege WMS User Manual

Detailed guide — v1.0

Professional warehouse management system with barcode and handheld support — designed for Saudi concrete plants, spare-parts workshops, and vehicle/machinery consumables.

Table of Contents

Overview
Quick start
Items
Locations
Purchase orders
Receiving
Sales orders
Picking
Pack & ship
Transfers
Cycle counts
Inventory
Totals
Reports
Purchase reconciliation
Barcodes & labels
Handheld (/m)

Settings
Users & roles
Integrations
Returns (RMA)
Quality (QC)
Dock scheduling
Yard
Labor
Replenishment
ZATCA
Languages
Detailed receiving
Detailed shipping
Detailed cycle count
Detailed move
Detailed adjust
Barcodes
Offline
Support

Overview

Storege WMS is a professional barcode + handheld warehouse management system for Saudi concrete plants, spare-parts workshops and vehicle consumables. 9 languages (Arabic/Urdu RTL), all prices in SAR, 15% tax.

Quick start

1) Sign in (admin@storege.app / Admin@12345). 2) Select a warehouse. 3) Add categories. 4) Add items (barcode/reorder). 5) Add locations (R01-C01). 6) Create PO. 7) Receive → putaway. 8) Create SO → allocate → pick → pack → ship.

Items

Manage SKU, EAN-13 barcode, cost/price, reorder point, strategic stock, max stock, reorder qty, lot/serial tracking, shelf life. CSV import/export. Search by barcode/code/name.

Locations

Multiple warehouses, zones, locations (PICK/DOCK/STAGING/SHIPPING/QUARANTINE), capacities, barcodes, rack/column (R01-C01).

Purchase orders

Create PO from supplier (items/qty/cost). ASN number + expected date. Partial/full receive. Cancel receive by reversing movements.

Receiving

Receive against PO, lot code/expiry/serials, choose location, putaway suggestion (consolidate/empty). Cross-dock.

Sales orders

Create SO from customer, FEFO auto-allocation, allocate stock, statuses OPEN/ALLOCATED/PICKING/PICKED/PACKED/SHIPPED. Priorities.

Picking

Pick tasks per allocation, picked quantities, staging location. Wave/Batch picking: combine multiple orders into one pick list (/wave-picking).

Pack & ship

Pack all lines, ship with carrier/tracking. Fields: issue reason (e.g. vehicle spare parts), vehicle/equipment (plate), delivered to. Print Issue Permit.

Transfers

Between warehouses: draft → in transit → receive. Lot/serial tracking.

Cycle counts

Count by location/zone/warehouse, enter counts, variances, approve to adjust stock. Blind counts + ABC.

Inventory

Real-time balance per item/location/lot/serial. Manual adjust with reason. Move. Stock ledger.

Totals

Aggregated view: units, SKUs, stock value, reserved/available, by warehouse/category, strategic alerts. Page /totals.

Reports

Stock valuation, low stock, expiry, movement, dead stock, productivity, top items, ABC, count accuracy, purchase reconciliation, wave picking.

Purchase reconciliation

Compare invoiced quantities vs received vs on-hand (variance/status). Page /reconciliation.

Barcodes & labels

Camera/USB scanner, EAN-13/Code128 generator, label designer, A4/thermal print, ZPL export.

Handheld (/m)

Mobile UI for receive, putaway, pick, count. Offline (IndexedDB) + queue + idempotency (X-Op-Id).

Settings

Company data, logo upload (650KB), currency (SAR), tax 15%, labels, barcode prefix. Logo shown in sidebar and dashboard.

Users & roles

ADMIN/MANAGER/OPERATOR/VIEWER. Permissions, audit log.

Integrations

API keys, webhooks. ZATCA Phase 2 (QR+XML), Salla/Zid, ERP/EDI/TMS in roadmap.

Returns (RMA)

Customer/supplier returns. Statuses DRAFT→RECEIVED→COMPLETED/CANCELLED. Disposition RESTOCK/SCRAP/QUARANTINE. Page /returns.

Quality (QC)

PENDING/PASSED/FAILED on received lines. Page /quality.

Dock scheduling

Book appointments for trucks/docks, status updates. Page /docks.

Yard

Track yard spots (EMPTY/OCCUPIED) and trailers. Page /yard.

Labor

Track tasks (PICK/PUTAWAY/COUNT/RECEIVE) and time/qty. Page /labor.

Replenishment

Suggestions to move stock from reserve to pick face. Page /replenishment.

ZATCA

QR (TLV base64) + UBL 2.1 XML, button on invoice + download XML. Saudi compliance.

Languages

9 languages (Arabic/Urdu RTL). Change from top selector.

Detailed receiving

1) Create PO. 2) Open PO → receive. 3) Enter received qty + lot/expiry/serials. 4) Choose location (DOCK/STAGING). 5) Submit. 6) Putaway (auto-suggest). 7) System creates Stock + StockMovement (RECEIVE).

Detailed shipping

1) SO in ALLOCATED/PICKED. 2) Pack all lines. 3) Ship: carrier/tracking. 4) Fields: issue reason (e.g. vehicle spare parts), vehicle/equipment (plate), delivered to. 5) System deducts from shipping area and creates Shipment + Issue Permit (print).

Detailed cycle count

1) Create Cycle Count (warehouse/zone/location). 2) System generates lines (expectedQty). 3) Enter countedQty. 4) Approve → adjusts Stock and creates COUNT movements. 5) Count accuracy report.

Detailed move

1) Open Inventory → select item/location. 2) Click Move. 3) Enter qty + destination location. 4) System decrements source and increments destination.

Detailed adjust

1) Open Inventory → Adjust. 2) Enter signed qty (+/-) + reason. 3) System updates Stock and creates ADJUST movement. 4) Audit log.

Barcodes

USB/Bluetooth scanner (Keyboard Wedge): scan then Enter. Camera scanner: camera button (HTTPS/localhost). Generate EAN-13/Code128. Label designer. A4/thermal print. ZPL export.

Offline


PWA + IndexedDB. After first open (online), caches items/locations/POs/picking/counts. When offline, receive/putaway/pick/count are queued. On reconnect, auto-sync. X-Op-Id prevents duplicates.

Support

Developed by FimtoSoft — www.fimtosoft.com. Manual: /manual. PDF: /storege-manual-ar.pdf. APK: GitHub Releases.



Warehouse flow: Receive → QC → Putaway → Storage → Pick → Pack → Ship



Storege WMS module map

Role Permission Matrix

	Read	Write	Manage	Settings	Users
ADMIN	1	1	1	1	1
MANAGER	1	1	1	1	0
OPERATOR	1	1	0	0	0
VIEWER	1	0	0	0	0

Role permission matrix

Developed by FimtoSoft — www.fimtosoft.com