## **Ping Setup Guide**

To configure SSO to log in to our application, you will need to add a new SAML Web App to your PingOne Console. This is typically performed by someone in IT or InfoSec who has administrative privileges to the PingOne Console account.

Follow the steps below to create an application with information we've generated for your account, and when finished be sure to return the Metadata XML to us so your team can begin signing in with SSO.

If you run into any trouble, contact us here and we'll get back to you as soon as we can:

# Step 1: Add a new SAML web app

Login to the PingOne Console: <a href="https://admin.pingone.com">https://admin.pingone.com</a>


1.


2.

3.

Click on Connections in the top navigation.

Under **Select an application type** click on the tile labeled WEB APP.





Step 2: Create app profile

- 1. In the field labeled **Application name**, enter: For the **Description** field, you can optionally enter a description for your colleagues describing what 2. the app is used for. 3. For the **Icon**, you can download one from the following URL, then upload it by clicking the + button.

Step 3: Configure SAML

When finished, click Next in the bottom right.

4.

### 1. In the **Configure SAML Connection** step, enter the following information in the respective fields:

**ACS URLS Entity ID** Assertion Validity Duration (in seconds) 60 2. All other fields should be left as is. 3. Click Save and continue. Step 4: Map attributes

## 2. Click PingOne Attribute.

Click + Add Attribute.

4. Input "id" in the blank text field, then check the **Required** box to the right of that input field.

SAML ATTRIBUTES

PINGONE USER ATTRIBUTE

User ID

Click + Add Attribute.

3.

7.

9.

5. 6. Click PingOne Attribute.

When completed, this is what you should see:

8. Input "email" in the blank text field, then check the Required box to the right of that input field.

APPLICATION ATTRIBUTE

APPLICATION ATTRIBUTE


Required

saml\_subject

From the dropdown menu under **PingOne User Attribute**, select **Email Address**.


From the dropdown menu under PingOne User Attribute, select User ID.

PINGONE USER ATTRIBUTE



Web App (SAML) DESCRIPTION: Not Set CLIENT ID: 72f9c7de-be98-478e-949c-2e10931a9368

Download



 ${\tt SINGLE\,LOGOUT\,SERVICE:} \qquad \text{https://auth.pingone.com/5fe5a1f5-a0be-4d76-995b-252bc0e23852/saml20/idp/slosely.}$ https://auth.pingone.com/5fe5a1f5-a0be-4d76-995b-252bc0e23852/saml20/idp/sso

us so we can complete the setup process. Then you'll be able to sign in to your new account.

Once the file has been downloaded to your computer, please attach it to an email and send it back to