

"Thank you for purchasing content timeline for wordpress. We hope that you will have fun with it as much as we had fun creating it."

- SHINDIRI STUDIO TEAM

TABLE OF CONTENTS

SECTION 1

INSTALLATION

1.1 WORDPRESS INSTALLATION 1.2 FTP INSTALLATION

SECTION 2

CREATING YOUR FIRST TIMELINE

2.1 - ADDING CONTENT FROM POST CATEGORIES

2.2 - ADDING MANUAL CONTENT

SECTION 3

MANAGING YOUR TIMELINES

3.1 - RE-ORDER, DELETE, ADD NEW

SECTION 4

SETTINGS

4.1 - GLOBAL SETTINGS

4.2 - CARD SETTINGS

4.3 - BUTTON SETTINGS

4.4 - FONT SETTINGS

SECTION 5

ADD A TIMELINE TO YOUR PAGE

5.1 - USING VISUAL COMPOSER 5.2 - WITHOUT PAGE BUILDER

SECTION 6 | UPDATING THE TIMELINE PLUGIN



INSTALLATION

When you download a full package from Codecanyon, un-zip it. Inside that .zip you will find another .zip archive named "ContentTimeline.zip", this is the actual plugin that you need to install.

There are 2 ways of installing Content Timeline:

SECTION 1.1

WORDPRESS INSTALLATION

Login to your Wordpress website backend and on the left menu you will find "Plugins" link. Hover that link and click "Add New" from a dropdown menu. On the top of the page with plugins click "Upload Plugin" button and click "Browse" and select "ContentTime-line.zip" file from your plugin folder and click "Install Now" button.

NOTE:

Depending on your hosting company and server settings you may or may not be prompted for a FTP password to your hosting. If you do not know your FTP username, host and password please contact your hosting provider.

SECTION 1.2

FTP INSTALLATION

Extract your "ContentTimeline.zip" into a separate folder. Login to your FTP account (using some FTP software, FileZilla is free and reliable) and browse to the location of your wordpress website. Once you are in the root of your wordpress installation folder open "wp-content" folder and inside it open "plugins" folder. Now copy your previously extracted folder to "plugins" folder and go to your Wordpress backend.

NOTE:

Some hosting companies have very high permissions set on their server. This means that you may not have high enough permission to paste files to your online folders. If this is the case, please contact your hosting provider and explain them that you need permissions to write on your server.



CREATING YOUR FIRST TIMELINE

Once the plugin is installed an activated you can proceed to create your first timeline. In the Wordpress backend click on the "Content Timeline" in the left menu and click "Add New" button on top of the page.

You are now located at the main page of your new timeline. Here you can set-up your timeline, add content and everything else that we will cover in the rest of this manual.

Lets start with naming your first timeline and adding some content to it. Type in a name of your new timeline in the field at the top of the page. There are 2 ways of adding content to your timeline:

SECTION 2.1

ADDING CONTENT FROM POST CATEGORIES

At the center of your page click the "Add New Item / Category" button. You can choose from 3 options, select "Whole Category" option and select a category from your existing ones to add to your timeline and click "Add" button. Once you have added the category to your new tiimeline a list of all posts from that category will appear bellow that button. You can now choose to click "Save Timeline" and preview it or you can expand each individual post and change some of its settings (image, title, excerpt, date, category, links).

Once an item is expanded you can set it to be a start item by selecting a checkbox "Start Item" on the far right of that particular post.

You can also "drag and drop" all posts to re-arrange them the way you want them.

NOTE:

If a post contains some HTML in it it may break the preview and excerpt txt. That can be fixed by manually editing that particular post from Content Timeline.

SECTION 2.2

ADDING CONTENT MANUALLY

At the center of your page click the "Add New Item / Category" button. You can choose from 3 options, select "Add New" and you will get a blank card with no content in it. Now you have the option to add cover image, active cover image, cover image link (pretty-Photo), title, content, date, category, excerpt text, content text, button URL, enable / disable scroll.

You can add as many custom cards as you want, you can also import a category and add custom cards to it.



MANAGING YOUR TIMELINES

You can have multiple timelines on your website with different settings each. In order to manage them you have a preview screen with all your created timelines. You can see this page by clicking "Content Timeline" link in Wordpress backend. On this page you can create new timelines, delete some of the existing ones and edit any timeline.



SETTINGS

SECTION 4.1

GLOBAL SETTINGS

Style: Choose one of the premade style for timeline layout. There are 14 different styles to choose from

Vertical: Switch timeline orientation to vertical

Disable Pretty Photo: Disable link on an image to open up a pretty photo gallery

Read More Link: Enable opening of a post in a new window instead of a preview

Scroll Speed: Set the speed of the horizontal scroll for the Timeline cards

Easing: Choose an easing of your scroll transition

Close Item on Transition: Check this box to disable an item being open when scrolling your cards

Latest Post is Start Item: Set the latest post that you added as a first item on the Timeline

Load Posts Dynamic: Check this box to enable a post to be added automatically to timeline once it is created in Wordpress

Switch Direction: Latest posts are located on the right

Autoplay: Check this box to enable autoplay

Autoplay Mobile: Check this box to enable autoplay on mobile devices only

Autoplay Step: Set the amount of delay for autoplay

Hide Years: Check this box to remove years from your timeline

Type: Choose the type of your timeline ordering: Years, Categories, Months

Timeline Width: Set the width of the entire timeline

Item Margin: Set the space between the cards

Item Height: Set the height for the cards in a timeline

Read More: Choose the option for your Read More button: Whole Item, Button, None

Hide Timeline / Navigation: Check this box to hide the timeline above the cards / hide navigation arrows

Line / Navigation Style: Choose the design for your timeline and navigation

Shadow: Set the shadow options for your cards: Show, Show on hover, Hide

Node Desctiption Color, Node Line Color: Set the colors for nods on the timeline and the line itself

Node Arrows Color, Node Dot Color: Set the colors for nod arrows and the dot itself



SETTINGS

SECTION 4.2

CARD SETTINGS

DEFAULT VIEW	ACTIVE VIEW
Card Width: Choose the width for your cards	Card Width: Choose the width for your cards
Content Padding: Choose the padding of all elements in a card	Content Padding: Choose the padding of all elements in a card
Image Height: Choose the height of an image in a card (if the image is not full width of the card)	Image Height: Choose the height of an image in a card (if the image is not full width of the card)
Image Border Width: Choose the width of the border bellow the image (0 = disabled)	Image Border Width: Choose the width of the border bellow the image (0 = disabled)
Image Border Color: Set the color of the border bellow the image	Image Border Color: Set the color of the border bellow the image
Show Date: Choose to display the date of a post on a card	Show Date: Choose to display the date of a post on a card
Background Color: Choose the background color for your cards	Background Color: Choose the background color for your cards
Background Image: Choose the background image for your cards	Background Image: Choose the background image for your cards
	Scroller Color: Choose the color of the scroller in an

active view of the card if there is more content to be

displayed then the height of the card is



SETTINGS

SECTION 4.3

BUTTON SETTINGS

Button Type: Choose the type of the button on your cards: Flat, Flat White, Sharp (when the button is selected as a "Read More" option)

Text: Type in the text that you want to display on your button (the default text is "Read More")

Close Text: Type in the text that you want to display on your close button (the button is located in the active view of any card)

Color: Choose the color for the buttons

Hovoer Color: Choose the hover color for the buttons

SECTION 4.4

FONT SETTINGS

TITLE

Title Font Size / Line Height: Choose the font size and line height (space between the rows) for the title

Title Font Type / Color: Choose the font type (Google fonts) and the color

TEXT

Text Font Size / Line Height: Choose the font size and line height (space between the rows) for the title

Text Font Type / Color: Choose the font type (Google fonts) and the color

OPEN TITLE

Open Title Alignment: Choose the alignment for the title: Left, Center, Right

Open Title Font Size / Line Height: Choose the font size and line height (space between the rows) for the title

Open Title Font Type / Color: Choose the font type (Google fonts) and the color

OPEN TEXT

Open Text Font Size / Line Height: Choose the font size and line height (space between the rows) for the title

Open Text Font Type / Color: Choose the font type (Google fonts) and the color



ADD A TIMELINE TO YOUR PAGE

When you are sattisfied with the look and feel of your Content Timeline it is time to publish it on your page of your website.

Two most common ways to add a Content Timeline to your website are:

SECTION 5.1

USING VISUAL COMPOSER

If you do not have an already existing page where you want your timeline to be placed you need to create a page in Wordpress. Go to "Pages" and click "Add New" button. Once on that page activate Visual Composer by clicking "Backend Editor" button. Now click the "Add Element" button and add "Text Block" shortcode. Now click "Content Timeline" button on the left Wordpress menu and open it in new window. Copy the shortcode for your timeline (it should look something like this [content_timeline id="1"]) and paste it in the "Text Block" shortcode on your page. Click "Save Changes" for that shortcode and update and preview your page. Your timeline should now be live and visible on your page.

SECTION 5.2

DEFAULT WORDPRESS PAGE

If you do not have an already existing page where you want your timeline to be placed you need to create a page in Wordpress. Go to "Pages" and click "Add New" button. Now click "Content Timeline" button on the left Wordpress menu and open it in new window.

Copy the shortcode for your timeline (it should look something like this [content_timeline id="1"]) and paste it on your page where ever you want it. Update and preview your page. Your timeline should now be live and visible on your page.



UPDATING THE TIMELINE PLUGIN

When updating to a newer version please read the CHANGELOG file to understand all changes made in order to know what has been updated, what are the new options, and stuff that you should pay attention to. If you're constantly updating your system (which is recommended) this file will help you a lot!

Follow the steps below to update Content Timeline plugin

- Navigate to Plugins admin menu
- Click Deactivate next to Content Timeline plugin name. After the plugin has been deactivated click Delete and then Yes delete all the files button
- After the plugin has been deleted repeat the process of installing plugin via WordPress from this documentation with new updated files.