
介绍

在hostA上使用docker标准安装时序数据库 Influxdb 和 VictoriaMetrics,然后使用docker安装一个容器性能分析工具 cAdvisor 来采集容器运行时的相关指标。



环境

- hostA: 178.104.163.175 2c 4g 服务: cadvisor、influxdb、VictoriaMetrics
- hostB: 178.104.163.111 2c 4g 服务: prometheus
- k8s集群: 178.104.163.88

开始

install cadvisor

```
docker run -d \
    --name cadvisor \
    -p 8080:8080 \
    -v /:/rootfs:ro \
    -v /var/run/:/var/run/:rw \
    -v /sys/:/sys/:ro \
    -v /var/lib/docker/:/var/lib/docker/:ro \
    -v /dev/disk/:/dev/disk/:ro \
    google/cadvisor:latest
```

• install influxdb

```
docker run -p 8086:8086 -d \
    --name influxdb \
    -v influxdb:/var/lib/influxdb \
    influxdb:1.8
```

```
docker run -p 8087:8086 -d \
     --name influxar \
     -v /root/influxar:/var/lib/influxdb \
     harbor.archeros.cn/library/influxdb:v1.6.0 cluster
docker run -p 8086:8086 -d \
     -v influxdb:/var/lib/influxdb \
     -v influxdb2:/var/lib/influxdb2 \
      -e DOCKER INFLUXDB INIT MODE=upgrade \
     -e DOCKER INFLUXDB INIT USERNAME=root \
      -e DOCKER INFLUXDB INIT PASSWORD=123456@qwe \
      -e DOCKER_INFLUXDB_INIT_ORG=my-org \
      -e DOCKER_INFLUXDB_INIT_BUCKET=my-bucket \
      influxdb:2.3
export INFLUX USERNAME=root
export INFLUX PASSWORD=123456@qwe
export DOCKER_INFLUXDB_INIT_USERNAME=root
export DOCKER INFLUXDB INIT PASSWORD=123456@qwe
influx config create --config-name config01 \
--host-url http://178.104.163.111:8086 \
--org my-org \
--token POPKjIwNmKKBga0CNrDWV4LlnEMY-
zcz6F79fYa8yTpHOBz72rxtYUJZ1kXiCsaMvWjrx57nkCHFKiXvdyuqGg== \
--active
influx write --bucket my-bucket --precision s "m v=2 $(date +%s)"
```

install VictoriaMetrics

```
docker run -it -d \
    --name vm \
    -v /root/victoria-metrics-data:/victoria-metrics-data \
    -p 8428:8428 \
    victoriametrics/victoria-metrics:latest
```

• install prometheus


```
docker run \
-p 9090:9090 \
-v /root/prometheus-2.36.2.linux-
amd64/prometheus.yml:/etc/prometheus/prometheus.yml \
prom/prometheus

将cadvisor的地址 178.104.163.175:8080 添加进prometheus.yml
```

测试结果



• CPU





Add Faller

使用率图表




内存








• 磁盘











[root@vm-3 victoria-metrics-data]# du -sh
165M .

root@3175a32c3dc1:/var/lib/influxdb# du -sh
1.7G .