Install Aufake3D in five steps

Beginner-friendly guide for the v0.8.18 runtime game kits. No coding required.

Before you start: Lower your headphone volume. Aufake3D defaults to a high gain (5.0). Back up your entire working game directory before any file copying.

1. Download and extract the compiled runtime ZIP, not the source-code ZIP.
2. Open the extracted Game_Kits folder.
3. Open the folder matching your game, then COPY_TO_GAME_FOLDER.
4. Copy the contents inside that folder beside your original game executable. Keep subfolders intact.
5. Double-click RUN_AUFAKE3D_WINDOWS.cmd in the game directory.

Which folder do I choose?

Game	Open this kit	Locate this real game file
Alice (2000)	Alice_2000	alice.exe
Alice (2011), VorpalFix 4.2.1	Alice_2011_VorpalFix	alice.exe in its bin folder
Quake III Arena 1.17	Quake_III_117	quake3.exe

The folder rule (important)

```
COPY FROM Game_Kits / Alice_2000 / COPY_TO_GAME_FOLDER / [contents]

COPY INTO Your game directory / alongside alice.exe
```

Do not: create a nested COPY_TO_GAME_FOLDER directory inside your game.

Alice 2011 exception: Do not start with step 4. First read page 3: you must save two copies of the original Miles DLL and verify your game version.

Alice (2000)

A quick manual copy into the folder containing the original alice.exe.

1. Back up your full Alice directory. Confirm the original alice.exe and SndDrivers/mss32.dll exist.
2. In the runtime, open Game_Kits / Alice_2000 / COPY_TO_GAME_FOLDER.
3. Select and copy all eight files into the directory that already contains your game executable.
4. Launch using RUN_AUFAKE3D_WINDOWS.cmd, not the original game shortcut.
5. On first Windows launch, A3D2 is set once in the saved config with a backup. From then on, changing providers in the game remains free and is never overridden.

Your game directory should now resemble this

```
alice.exe [ORIGINAL GAME]

a3d.dll a3dapi.dll [AUFAKE3D]

alice-a3d-bridge.exe [AUFAKE3D]

alice-a3d-bridge.exe.manifest [AUFAKE3D]

alice.exe.manifest [AUFAKE3D]

AUFAKE3D_SET_INITIAL_A3D2.ps1 [ONE-TIME DEFAULT]

RUN_AUFAKE3D_WINDOWS.cmd [LAUNCH THIS]

RUN_AUFAKE3D_WINE.sh [LINUX/WINE]
```

Already have an alice.exe.manifest? Make a backup and check what it belongs to before replacing it. Never overwrite the original alice.exe.

What should happen?

A3D2 should be selected on the first launch. Later Miles/Dolby selections remain respected. This default setup does not inject +set s_milesdriver a3d2. The WaveOut queue remains 6 × 256 frames (32 ms at 48 kHz).

Release-candidate note: Alice 2000 bidirectional sound-provider switching has been checked in source but still needs a complete gameplay round-trip validation.

Alice (2011) + VorpalFix 4.2.1

This kit needs two extra preparations. Do them before copying any Aufake3D files.

STOP: version-specific kit. You must have the known Alice 2011 build, VorpalFix files winmm.dll and VorpalFix.ini, and the original SndDrivers/mssa3d2.m3d. Your Miles DLL must be the real game-owned DLL, not an older Aufake3D proxy.

1. Back up your whole game bin directory. Check these original SHA-256 values in PowerShell:

```
Get-FileHash -Algorithm SHA256 .\alice.exe

Get-FileHash -Algorithm SHA256 .\SndDrivers\mss32.dll

alice.exe SHA-256:

08bcbe4b549633b24c90a1ab36bf516bd8873432c68b37248c98ee4225506e50

SndDrivers/mss32.dll SHA-256:

14fb663762695a02e06b144c487254b08163185fa009efb32df733882cd570de
```

If either fingerprint differs, do not use this version-specific kit.

2. Make two renamed copies of the verified ORIGINAL SndDrivers\mss32.dll:

```
SndDrivers\mss32.dll → a3d_mss_real.dll

SndDrivers\mss32.dll → SndDrivers\a3d_mss_real.dll
```

3. Back up any existing root mss32.dll. Then copy everything from Game_Kits / Alice_2011_VorpalFix / COPY_TO_GAME_FOLDER into the bin folder beside alice.exe. Merge SndDrivers; do not replace the entire folder.

4. Check that both saved a3d_mss_real.dll files remain present and original. Do not delete mssa3d2.m3d, winmm.dll or VorpalFix.ini.

5. Make sure alice.exe.manifest does not already exist. The launcher makes a temporary copy and refuses to overwrite another manifest.

6. Double-click RUN_AUFAKE3D_WINDOWS.cmd. On first launch, its PowerShell helper sets A3D2 in saved config once, with a backup. After that, all provider choices remain under the game menu.

Expected: A3D2 initially; Miles 2D ↔ A3D2 ↔ Dolby still switch freely afterward. A3D2 initialisation happens only once by saved config: no forced startup parameter. This new integration needs real-game verification.

Quake III Arena 1.17

A straightforward five-file copy, with one in-game audio setting.

1. Back up your full Quake III folder. Confirm you have the original quake3.exe and matching baseq3/pak*.pk3 game data for version 1.17.
2. Open Game_Kits / Quake_III_117 / COPY_TO_GAME_FOLDER.
3. Copy all five files beside quake3.exe: a3d.dll, a3dapi.dll, quake3.exe.manifest, RUN_AUFAKE3D_WINDOWS.cmd and RUN_AUFAKE3D_WINE.sh.
4. Double-click RUN_AUFAKE3D_WINDOWS.cmd.
5. Open the game console; enter s_enable_a3d 1. Restart sound or the game if prompted.

Game directory after copying

```
quake3.exe [ORIGINAL GAME]
baseq3\pak*.pk3 [ORIGINAL GAME DATA]
a3d.dll a3dapi.dll [AUFAKE3D]
quake3.exe.manifest [AUFAKE3D]
RUN_AUFAKE3D_WINDOWS.cmd [LAUNCH THIS]
RUN_AUFAKE3D_WINE.sh [LINUX/WINE]
```

Fast troubleshooting

Symptom	Check
Game EXE not found	You copied to the wrong directory. Use the folder holding the original EXE.
DLL or bridge missing	Copy the entire correct kit, not just a3d.dll.
Alice 2011 Miles error	Restore the original Miles DLL and make the two renamed copies.
Alice 2011 manifest error	Do not overwrite an existing alice.exe.manifest; investigate/backup it.
Quake III fails before gameplay	Verify matching original 1.17 PK3 files.

To uninstall a manually copied kit: Restore your complete pre-installation game-folder backup. Manual copying has no automatic rollback receipt. Never delete your original game EXE, game data or vendor-owned DLLs.

Linux/Wine: Copy the same kit, then run bash `./RUN_AUFAKE3D_WINE.sh` from the game folder. Alice 2011 under Wine is experimental. See the full manual in the original runtime ZIP.