

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Bitfinex sub-account

Updated 1 year ago

Overview

Fireblocks supports Bitfinex sub-accounts via exchange connectivity. Connect the exchange, and rebalance securely between your exchange's main account and sub-accounts on Fireblocks.

Important

- If you already have a Bitfinex sub-account connected to this workspace, you must remove it and then reconnect it.
- If you have a Bitfinex main account connected, you may need to remove it if the email field was left blank.

Configuring your Bitfinex sub-accounts

To configure your Bitfinex sub-account to connect to Fireblocks:

1. Refer to [Bitfinex.com API Documentation](#) for instructions on how to create a sub-account.
2. When presented with them, enable the following toggles:
 - a. **Account info** (top toggle only)
 - b. **Account history**
 - c. **Wallets** (for both toggles)
 - d. **Withdraw**
3. When prompted to do so, name your new API Key "Fireblocks."
4. Copy and keep a record of both the API Key and Secret Key. You will need them when adding this exchange to your workspace.

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



2. Select **+ Connect Account**.

3. Select Bitfinex, select Sub account, and then complete the following fields:

- a. **Account name:** Enter the Account Name you want to give this exchange sub-account on Fireblocks.
- b. Select the main account you want to connect to this sub-account.
Remember, your main account must be connected to Fireblocks *before* you can connect a sub-account.
- c. **API key:** Enter the API key that you saved from Bitfinex.
- d. **Secret Key:** Enter the Secret key that you saved from Bitfinex.
- e. **Email:** Enter the same email account you used to register your Bitfinex account.
- f. Select **Connect Account**.

The [admin quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Bitfinex sub-account appears on the Exchanges page along with all managed assets and their balances. Following admin quorum approval, transfers will be available between this sub-account and its Bitfinex main account.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Bitfinex sub-accounts

Configuring Fireblocks

Related Articles



Coinbase Pro and Coinbase Exchange sub-accounts



Crypto.com sub-account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

-  HTX (formerly Huobi) sub-account
-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account
-  OKX (OKEx) - API V5 sub-account
-  Bitstamp sub-account
-  Bitfinex account
-  Bybit sub-account
-  Binance sub-account
-  Binance.US sub-account
-  Bitget sub-account



fireblocks.com

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)