

Don't see what you're looking for? Log in for the full Help Center experience

Bitget sub-account

Updated 10 months ago

Overview

Fireblocks supports Bitget sub-accounts via exchange connectivity. Connect the exchange, and rebalance securely between your exchange's main account and sub-accounts on Fireblocks.

Configuring your Bitget sub-account

To configure your Bitget sub-account to connect to Fireblocks:

1. Refer to the [Bitget API Documentation](#) for instructions on creating a sub-account.
2. Copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.
3. Make sure you enable the following permissions in **Read-write** mode:
 - Futures > **Orders, Holdings**
 - Spot > **Trade**
 - Margin > **Trade**
 - Wallet > **Transfer, Withdraw**
4. Under the **Link IP address** field, enter: **18.117.33.242**.
5. Under IP access restrictions, enter **52.76.208.129** in place of 0.0.0.0.

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Exchanges**.
2. Select **+ Connect Account**.
3. Select **Bitget**, select Sub account, and then complete the following fields:
 - a. **Account Name:** Enter the name you want to give this exchange sub-account in your workspace.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

e. **UID:** Enter the UID of this sub-account, found in your Bitget account portal.

4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Bitget sub-account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers will be available between this sub-account and its Bitget main account.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Bitget sub-account

Configuring Fireblocks

Related Articles

-  Bitstamp sub-account
-  Bitget account
-  Bybit sub-account
-  Coinbase Pro and Coinbase Exchange sub-accounts
-  Crypto.com sub-account
-  Coinhako sub-account
-  Deribit sub-account
-  Gate.io sub-account
-  HTX (formerly Huobi) sub-account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account
-  OKX (OKEx) - API V5 sub-account



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)