

Don't see what you're looking for? Log in for the full Help Center experience

Cross-chain bridging in Fireblocks

Updated 12 days ago

Overview

You can use Fireblocks to move supported assets across EVM-compatible networks. Fireblocks facilitates bridging through an external bridge aggregator which evaluates available routes and provides the bridging path (powered by [LI.FI](#)). Fireblocks then executes each required step automatically.

Cross-chain bridging is available in the Console and via the [Fireblocks APIs and SDKs](#).

Supported assets and networks

Source and destination networks

We currently support bridging between the following networks:

- Arbitrum One
- Base
- Binance Smart Chains
- Blast
- Ethereum
- HyperEVM
- Optimism
- Polygon
- Unichain
- Worldchain
- zkSync

Supported assets

We currently support bridging of all assets (both native and tokens) that are supported by the underlying bridging providers (e.g., USDC, USDT, ETH, WETH, DAI, WBTC). Our current support is for moving the same asset between different blockchains. Bridge+swap is

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Supported bridges

We currently support the Across bridge provider via [Li.fi](#).

To request additional bridge providers, contact your [Customer Success Manager](#).

Notes:

- Some Li.Fi-supported bridges may not be available in Fireblocks due to security, liquidity, or compliance requirements.
- The routing engine selects the best available route based on fees, liquidity, timing, and slippage.

Prerequisites

Policy

Your policy must allow bridging for supported assets and routes. Ensure you have policy rules permitting:

- Approve
- Typed messages (Permit)
- Contract calls

Exact-amount and Permit2 approvals

Fireblocks may set an unlimited allowance for the Permit2 contract only, which is required for enabling Permit2-based bridge operations. If the workspace has an [allowance cap configured](#), Fireblocks applies that cap instead of an unlimited allowance.

In all other cases, Fireblocks requests an exact-amount ERC-20 approval for the asset being swapped.

Starting cross-chain bridging

1. Select the Swap page

- In the Console, go to the Swap page.

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

CHOOSE THE NETWORK AND THE SAME ASSET YOU WANT TO RECEIVE. ENSURE YOU SELECT A supported asset-and-chain combination (e.g., USDC on Ethereum > USDC on Arbitrum). Note that on the "Receive" (to) asset, you must search for the same asset as the "Pay" (from) asset, just on another chain.

Q Search

All

Ethereum

Cross-chain

Arbitrum

Avalanche

Base

Optimism

Polygon

ZKsync

Popular assets



ETH (Ether)
Ethereum

134.05 ETH



USDC (USD Coin)
Ethereum

23.03 USDT



POL (Polygon)
Ethereum

12,149.03 POL



WETH (Wrapped Ether)
Ethereum

12,149.03 WETH



DOGE
Ethereum

12,149.03 DOGE



AVAX (Avalanche)

12,149.03 AVAX

3. Review the route

Fireblocks presents:

- Estimated output
- Fees (gas, provider)
- Slippage
- Required steps: Approve > Permit > Contract call > Bridge

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

The screenshot displays the Fireblocks Swap interface. On the left, the 'Pay' section shows a balance of 28.91454 and a transaction of 1 USDC (USD Coin) on the Ethereum network. The 'Receive (estimated)' section shows a balance of 0 and a transaction of 8.515541 POL (Polygon Ethereum) on the Ethereum network. The slippage tolerance is set to 0.5%. Below this, a summary shows '1 USDC = 8.515541 POL' using 'Uniswap Classic'. A 'Swap' button is visible. On the right, a list of recent swaps is shown, including transactions from Ethereum to Polygon, Ethereum to Ethereum, and Ethereum to Arbitrum One.

Swap Details:

- Pay:** 1 USDC (USD Coin) on Ethereum. Balance: 28.91454.
- Receive (estimated):** 8.515541 POL (Polygon Ethereum) on Ethereum. Balance: 0.
- Slippage tolerance:** 0.5%.
- Summary:** 1 USDC = 8.515541 POL. Provider: Uniswap Classic.
- Buttons:** Clear, Swap.

Recent Swaps:

- 1 USDC (Ethereum) → 0.995672 POL (Polygon)
- 0.01 ETH (Ethereum) → 169.265635... ETH (Ethereum)
- 0.01 ETH (Ethereum) → 0.18910325... ETH (Ethereum)
- 0.002 ETH (Ethereum) → 0.00199681 POL (Polygon)
- 0.001 ETH (Ethereum) → 0.00099838 WBT (Arbitrum One)
- 0.0001 ETH (Ethereum) → 2.03678917... ETH (Ethereum)
- 0.001 ETH (Arbitrum One) → 2.925197 ETH (Arbitrum One)
- 0.005 ETH (Arbitrum One) → 0.0049888... ETH (Arbitrum One)


Initiated 2:04 PM by eden katabi
[Show last step in transaction history](#)

[Learn more about swapping on Fireblocks](#)

First-time use: Terms & Conditions

On your first cross-chain bridging, a required Terms & Conditions agreement appears. You must acknowledge that the service is provided by a third-party provider and accept the associated Terms of Service and Privacy Policy before proceeding.

Don't see what you're looking for? Log in for the full Help Center experience



Executing the swap

When you confirm the order, Fireblocks performs the required operations in sequence. Depending on the route, you may need to sign:

1. Approve

- Required for ERC-20 tokens (e.g., USDC, USDT).
- Approves exact amount, one time, per token, per chain.

2. Permit (Typed message)

- EIP-712 typed message.
- Required only for ERC-20 tokens that use Permit2 for the approval flow.
- Not used for native assets (for example, ETH).
- Typed messages are used to sign Permit allowances, which authorize the smart contract (via Permit2) to move the approved tokens. Permit allowances combine the approval and the transaction setup into a single operation.

3. Contract call

Executes the bridging transactions on the source chain.

4. Bridge execution

Bridge execution is a background operation and does not require you to sign anything. It executes the cross-chain transfer via Across.


All required signing actions appear on the mobile app.

Monitoring your swap

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help C

/



Stages include:

- Approve (one time, per token per chain; only for tokens)
- Permit (only for tokens)
- Contract Call
- Bridge/Execute

You can now select the swap in Recent swaps to view full details.

Fees

Cross-chain bridging may include one or more of the following:

- Source chain approve gas fee (one time, per token, per chain)
- Source chain contract call gas fee
- Provider fees:
 - Aggregator fixed fee (e.g., LI.FI)
 - Relay fees: one covers gas expense on destination chain, and the other is for settling the transaction
 - Fireblocks fee

Note

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

- Estimated output
- Combined slippage
- All route-level fees

Vault account

Staking Production

Pay

Balance: 25.41261

ETH (Ether)

Ethereum

0.05

\$146.78

Receive (estimated)

Balance: 0.064383

ETH (Ether)

Base

0.049931

\$146.58

Slippage tolerance

0.5 %

1 ETH = 0.998637 ETH

Route

Across (via LiFi)

Minimum received

~0.04993 ETH

Provider fee

\$0.2

Total network fee

\$0.02

Clear

Swap

Swap statuses

- **Creating:** Fireblocks is creating the swap you initiated.
- **Pending approval:** The Approve transaction must be signed before the swap can proceed.
- **Pending permit:** The Permit allowance typed message must be signed before the swap can proceed.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

- **Canceled:** The swap was canceled.
- **Failed:** The swap could not be completed.

Completed and failed bridgings are removed from the Recent bridgings tab after 48 hours.

API and SDK support

Developers can:

- /createQuote
- /executeOrder
- Then, for tracking, they can:
 - /getOrders, or;
 - /getOrderById

Each endpoint provides full visibility into route details, timing, steps, and fees.

Full API documentation is available in the [Developer Portal](#).

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Supported assets and networks

Supported bridges

Prerequisites

Starting cross-chain bridging

Executing the swap

Monitoring your swap

Fees

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Related Articles

-  Transferring assets between networks
-  Swapping tokens on Fireblocks



[fireblocks.com](#) [Status](#) [API Docs](#) [Console](#) info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)