

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Default Gas Station values

Updated 3 days ago

Newer workspaces use Gas Station 2.0

If your workspace was created in January 2024 or later, refer to the [Gas Station 2.0 setup documentation](#).

You can configure the Fireblocks Gas Station with a gas threshold, a gas cap, and a maximum gas price for each blockchain network according to its base asset by using the Fireblocks API. Learn more about [Gas Station configuration in the Fireblocks Developer Portal](#).

When an incoming token deposit or an outgoing token withdrawal is detected, the Gas Station checks the gas balance of the vault account. If the balance is below the minimum gas threshold, it automatically fuels the vault account with the set maximum gas cap.

Default Gas Station values

The Gas Station automatically uses the default values below if you do not specify these parameters. Any EVM-based blockchain not listed in this table has the same values as those shown for Ethereum.

Note that the default value is null for the **Max gas price** setting. This means the Gas Station wallet will always top off no matter the current gas price.

Mainnet networks

Important

The Gas Station supports all EVM assets by default and uses the same parameters as Ethereum for all of them. Therefore, only EVMs with different default parameters appear in the table below.

Network	Base asset	Gas threshold	Gas cap	Max gas price
For most newly supported assets see supported blockchain networks				

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Base	ETH	0.005	0.01	NULL
Binance Smart Chain	BNB	0.0005	0.001	NULL
CELO	CELO	0.0001	0.0005	NULL
CELO ALF	CELO	0.0001	0.0005	NULL
CELO BAK	CELO	0.0001	0.0005	NULL
Ethereum	ETH	0.005	0.01	NULL
Ethereum AETH	ETH	0.0001	0.0005	NULL
Ethereum AETH_RIN	ETH	0.0001	0.0005	NULL
FANTOM	FTM	0.2	1	NULL
Humanity	H	0.005	0.01	NULL
Immutable zkEVM	IMX	0.005	0.01	NULL
Lumia	LUMIA	0.005	0.01	NULL
POLYGON	MATIC	0.005	0.01	NULL
Songbird	SGB	0.05	0.1	NULL
Songbird Legacy	SGB	0.05	0.1	NULL
TRON	TRX	10	60	NULL
WorldMobile	WMTX	0.005	0.01	NULL

Testnet networks

Network	Base asset	Gas threshold	Gas cap	Max gas price
Avalanche Test	AVAX	0.0005	0.001	NULL
Binance Smart Chain Test	BNB	0.0005	0.001	NULL

Note

TRON (TRX) is only compatible with Fireblocks Gas Station 2.0.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

they will *not* be overwritten.

Was this article helpful?

Yes

No

Related Articles

-  Set Up the Gas Station
-  My Gas Station is configured properly but a transfer failed due to insufficient funds for fees
-  General troubleshooting for the Gas Station
-  About the Gas Station
-  Enable the Gas Station
-  Setup for Gas Station 2.0
-  Configure Gas Station settings
-  About the Fireblocks Gasless Service
-  Enable or disable Gas Station auto-fueling
-  Gas Station Autoboot
-  View vault accounts with auto-fueling enabled
-  Fund the Gas Station
-  I received a deposit but the Gas Station didn't send any gas
-  View the Gas Station's current balance
-  Fireblocks Gas Station Transfers Source Type (November 2023)

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)