

Don't see what you're looking for? Log in for the full Help Center experience

EVM fees: Ethereum fee parameters

Updated 2 years ago

Available fee parameters

The following fee parameters are available for all transactions. However, only some parameters are necessary for each transaction depending on the blockchain.

Account-based fee parameters

All transactions

- **feeLevel** (LOW / MEDIUM / HIGH): For Ethereum only. This is the same as the tentative fee in the Console. Fireblocks uses the 12 most recent blocks to calculate fees, which vary based on the selected transaction speed. [Learn more about how preset fees are calculated.](#)
- **maxFee** (gwei): The maximum fee that should be paid for the transaction. Only set if requested.
- **gasLimit*** (gas): For EVM only. Units of gas required to process the transaction.
- **networkFee*** (Ether or equivalent): The total transaction fee in the blockchain's largest unit.

EIP-1559 transactions

- **priorityFee** (gwei): The maximum allowed priority fee as defined in EIP-1559. The priorityFee is automatically calculated based on the selected preset fee. If no preset fee is selected, the preset fee for medium transaction speed is used by default.
- **maxFee** (**maxFeePerGas**): The maximum value an initiator is willing to pay per gas unit. This includes both the **baseBlockFee** and **priorityFee**. The transaction sender is refunded the difference between the max fee and the sum of the base fee and tip. You can submit transactions with a **maxFeePerGas** corresponding to how much you are willing to pay for the transaction to be executed. This way, you know that you will not pay more than the market price for gas (**baseFeePerGas**) and will be refunded any extra funds. minus your tip.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



Non EIP-1559 transactions

- **gasPrice * (gwei)**: Price per gas unit. If both **networkFee** and **gasLimit** are specified, the **gasPrice** is defined automatically.
- **failOnLowFee (true / false)**: The medium calculated **gasPrice** and the set **gasPrice** of the transaction are compared. The allowed delta is calculated as a function of the **gasPrice**. If the difference is larger than the delta, the transaction will automatically fail.

* Only two out of three of these parameters may be set at any time.

The **gasPrice** and **priorityFee** parameters are automatically calculated based on the transaction speed selected in the **feeLevel** parameter.

Was this article helpful?

Yes

No

ON THIS PAGE

Available fee parameters

Account-based fee parameters

Related Articles

-  [EVM fees: Fee rates](#)
-  [EVM fees: Fee validation](#)
-  [EVM fees: Fee behavior](#)
-  [EVM fees: Overview](#)
-  [EVM fees: Selecting transaction fees](#)
-  [EVM fees: Net vs. gross fee selection](#)
-  [EVM fees: Adjusting network transaction fees](#)

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)