

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

[Fireblocks Help Center](#)

[Tokenization](#)

Non-EVM tokenization

Tokenization on Ripple

Note

Tokenization is a premium feature that requires an additional purchase. To add this feature, contact your [Customer Success Manager](#).

Overview

The Ripple network allows you to create, transfer, and trade custom tokens. Tokens you create on the Ripple network can be stored, transferred, and managed using Fireblocks.

Tokenization on Ripple using Fireblocks is a five-step process:

1. Creating an issuing account for the token
2. Adding the token to your Fireblocks workspace
3. Creating a distribution account for the token
4. Minting the token
5. Distributing tokens to other wallets.

Depending on the use case, it is also possible to burn tokens if there is no longer any need for them.

Learn more about the Ripple minimum balances.

Creating an issuing account for the token

Create an XRP asset wallet in a vault account (this will be referred to as Vault A). For a Ripple wallet to remain active, you must deposit and maintain a minimum balance of 1 XRP in it at all times. You must also maintain additional funds to finance fees for any future transactions.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Note:

The issuer address cannot hold a balance of its own token.

Adding the token to a Fireblocks workspace

Once the XRP wallet is funded, create your token using [the Tokenization page](#). You can also issue Ripple tokens using [the Fireblocks API](#).

Note:

At this point, the token is only listed in your workspace and has not been created on the Ripple network.

Adding the Ripple tokens is done in one of the following ways:

1. If you own the token, you can use the Console with the tokenization navigation page.
2. If you don't own the token, you can [submit a request for Fireblocks Support](#) to add support for that Ripple token.

After the token is recognized in your workspace:

1. Adding it to a vault account requires an on-chain operation. If you add the asset wallet to a vault account, your mobile app will receive a request to approve the token. This then creates an "enable asset" operation. This appears as a separate transaction in the recent activity panel and in your transaction history.
2. You can add the asset to a whitelisted wallet. There is no need for an additional tag or memo.

Creating a distribution account for the token

After your token is listed in Vault A:

1. Create an XRP wallet and a wallet for the new token in a different vault account (Vault B). A trust line is automatically established between the issuing XRP wallet in

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Minting the token

To mint the new token to the Ripple network, send the number of new tokens you want to create from the issuing account to the distribution account. The tokens are created and can be transferred to other wallets. [Learn more about minting tokens.](#)

You can also mint tokens directly to other internal or external Ripple wallets if a trust line has been established from those additional wallets.

Note:

You can also initiate this transaction by specifying the `TransactionOperation` object parameter as "MINT" in the Fireblocks API.

Distributing tokens to other wallets

After minting, you can send the new tokens from the distribution account to any Ripple wallet with an established trust line. You can establish a trust line automatically by adding the asset to the new wallet that will receive the token.

Note:

Tokens can be distributed using the Fireblocks Console or the Fireblocks API.

Burning tokens

Depending on the use case of the asset, you may want to burn tokens. You can burn tokens using the Fireblocks Console or the Fireblocks API.

[Learn more about burning tokens.](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

are not supported natively but can be completed using [Raw Signing](#). To enable raw signing, submit a request to your [Customer Success Manager](#).

- You can verify your token's creation on the XRP network using any XRPL block explorer including:
 - <https://livenet.xrpl.org/>
 - <https://xrpscan.com/>
 - <https://blockchair.com/ripple>

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Creating an issuing account for the token

Adding the token to a Fireblocks workspace

Creating a distribution account for the token

Minting the token

Distributing tokens to other wallets

Burning tokens

Additional information

Related Articles

-  Near tokens initial deposit
-  Removing a Ripple (XRP) trust line
-  Tokenization on Stellar
-  Blockchain Bond Tokenization Best Practices
-  About tokenization on Fireblocks

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Why does my token contract show a different address for roles?
-  Issuing tokens
-  Minting and burning tokens
-  Tokenization on EVM-compatible blockchains



[fireblocks.com](#) [Status](#) [API Docs](#) [Console](#) [info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)